Java API User's Guide

How to Locate API

• To Locate a Package:

Go to the Package Index

• To Locate a Class or Interface:

Go to the Class Hierarchy and then use "Find" in your browser. Once you're at a class page, use the Next/Previous links to browse through classes in that package alphabetically. The link called "This Package" in the navigation bar takes you to the list of classes in that package.

• To Locate a Method, Field or Constructor:

Use the Index of Fields and Methods

How This Document Is Organized

This document has three types of pages, corresponding to three different levels of API, plus a class hierarchy and an index of fields and methods.

Level 1 - All Packages

Example: Java Platform Core API

This page provides a list of all packages and is the front page of this document.

Level 2 - All Classes and Interfaces within a Package

Example: Package java.awt

This type of page provides links to the public classes and interfaces in a given package. It can contain four categories:

- Interfaces
- Classes
- Exceptions
- Errors

Level 3 - A Single Class or Interface

Example: Class Label

Near the top of the page is a class inheritance diagram, starting with java.lang.Object and ending with the class or interface. This is followed by the class declaration and a general class description.

Following this are two sections: the indexes for this page, followed by detailed descriptions. (Each index entry contains the first sentence from the detailed description for that item.) The index entries are alphabetical, while the detailed descriptions are in the order they appear in the source code. This is done to preserve the logical groupings established by the programmer. These are the categories, in order (where a category is omitted when it has no entries):

- Field Index
- Constructor Index
- Method Index
- Fields
- Constructors
- Methods

The fields, constructors and methods have additional color coding as follows:

[IMAGE] Instance Variable (Non-Static Field)
[IMAGE] Static Field (Class Variable)
[IMAGE] Constructor
[IMAGE] Instance Method (Non-Static Method)
[IMAGE] Class Method (Static Method)

Class Hierarchy

The Class Hierarchy contains a list of all the classes and interfaces starting with java.lang.Object, organized first by their inheritance structure, and within that structure sorted alphabetically by class or interface. Most every page has a "Class Hierarchy" link in the navigation bar to get to this page.

Index of Fields and Methods

The Index of Fields and Methods contains a list of all fields, methods and constructors, sorted alphabetically. Most every page has an "Index" link in the navigation bar to get to this page.

Submit a bug or feature

A B C D E F G H I J K L M N O P Q R S T U V W X Y Z

Index of all Fields and Methods

A

addController(Controller). Method in interface javax.media.Player Assume control of another Controller.

addControllerListener(ControllerListener). Method in interface javax.media.Controller Specify a ControllerListener to which this Controller will send events.

addGainChangeListener(GainChangeListener). Method in interface javax.media.GainControl Register for gain change update events.

С

CachingControlEvent(Controller, CachingControl, long). Constructor for class
javax.media.CachingControlEvent
Construct a CachingControlEvent from the required elements.
ClockStartedError(). Constructor for class javax.media.ClockStartedError
Construct a ClockStartedError with no message.
ClockStartedError(String). Constructor for class javax.media.ClockStartedError
Construct a ClockStartedError that contains the specified reason message.
ClockStoppedException(). Constructor for class javax.media.ClockStoppedException
ClockStoppedException(String). Constructor for class javax.media.ClockStoppedException
close(). Method in interface javax.media.Controller
Release all resources and cease all activity.
commitContentPrefixList(). Static method in class javax.media.PackageManager
Make changes to the content prefix-list persistent.
commitProtocolPrefixList(). Static method in class javax.media.PackageManager
Make changes to the protocol package-prefix list persistent.
conn. Variable in class javax.media.protocol.URLDataSource
connect(). Method in class javax.media.protocol.DataSource
Open a connection to the source described by the MediaLocator.
connect(). Method in class javax.media.protocol.URLDataSource
Initialize the connection with the source.
connected. Variable in class javax.media.protocol.URLDataSource
ConnectionErrorEvent(Controller). Constructor for class javax.media.ConnectionErrorEvent
ConnectionErrorEvent(Controller, String). Constructor for class javax.media.ConnectionErrorEven
CONTENT_UNKNOWN. Static variable in class javax.media.protocol.ContentDescriptor
ContentDescriptor(String). Constructor for class javax.media.protocol.ContentDescriptor
Create a content descriptor with the specified name.
contentType. Variable in class javax.media.protocol.URLDataSource
ControllerClosedEvent(Controller). Constructor for class javax.media.ControllerClosedEvent
Construct a ControllerClosedEvent.

ControllerClosedEvent(Controller, String). Constructor for class javax.media.ControllerClosedEvent ControllerErrorEvent(Controller). Constructor for class javax.media.ControllerErrorEvent ControllerErrorEvent(Controller, String). Constructor for class javax.media.ControllerErrorEvent ControllerEvent(Controller). Constructor for class javax.media.ControllerEvent controllerUpdate(ControllerEvent). Method in interface javax.media.ControllerListener This method is called when an event is generated by a Controller that this listener is registered with. createDataSource(MediaLocator). Static method in class javax.media.Manager Create a DataSource for the specified media. createDataSource(URL). Static method in class javax.media.Manager Create a DataSource for the specified media. createPlayer(DataSource). Static method in class javax.media.Manager Create a Player for the DataSource. createPlayer(MediaLocator). Static method in class javax.media.Manager Create a Player for the specified media. createPlayer(URL). Static method in class javax.media.Manager Create a Player for the specified media.

D

E

EndOfMediaEvent(Controller, int, int, int, Time). Constructor for class javax.media.EndOfMediaEvent **endOfStream**(). Method in interface javax.media.protocol.SourceStream

Find out if the end of the stream has been reached.

G

gainChange(GainChangeEvent). Method in interface javax.media.GainChangeListener This method is called to deliver a GainChangeEvent when the state of a GainControl changes.

GainChangeEvent(GainControl, boolean, float, float). Constructor for class javax.media.GainChangeEvent

getCachingControl(). Method in class javax.media.CachingControlEvent Get the CachingControl object that generated the event.

- **getContentDescriptor**(). Method in interface javax.media.protocol.SourceStream Get the current content type for this stream.
- **getContentLength**(). Method in interface javax.media.CachingControl Get the total number of bytes in the media being downloaded.
- getContentLength(). Method in interface javax.media.protocol.SourceStream Get the size, in bytes, of the content on this stream.
- getContentPrefixList(). Static method in class javax.media.PackageManager Get the current value of the content package-prefix list.
- getContentProgress(). Method in interface javax.media.CachingControl Get the total number of bytes of media data that have been downloaded so far.

getContentProgress(). Method in class javax.media.CachingControlEvent Get the total number of bytes of media data that have been downloaded so far.

getContentType(). Method in class javax.media.protocol.ContentDescriptor Obtain a string that represents the content-name for this descriptor.

getContentType(). Method in class javax.media.protocol.DataSource Get a string that describes the content-type of the media that the source is providing.

- getContentType(). Method in class javax.media.protocol.URLDataSource Return the content type name.
- **getControl**(String). Method in interface javax.media.Controller Get the Control that supports the class or interface specified.
- **getControl**(String). Method in interface javax.media.protocol.Controls Obtain the object that implements the specified Class or Interface The full class or interface name must be used.
- **getControl**(String). Method in class javax.media.protocol.URLDataSource Returns null, because this source doesn't provide any controls.
- getControlComponent(). Method in interface javax.media.CachingControl Get a Component that provides additional download control.
- getControlComponent(). Method in interface javax.media.Control Get the Component associated with this Control object.

getControlPanelComponent(). Method in interface javax.media.Player Obtain the Component that provides the default user interface for controlling this Player.

getControls(). Method in interface javax.media.Controller

Get a list of the Control objects that this Controller supports.

getControls(). Method in interface javax.media.protocol.Controls

Obtain the collection of objects that control the object that implements this interface.

getControls(). Method in class javax.media.protocol.URLDataSource

Returns an empty array, because this source doesn't provide any controls.

```
getCurrentRate(). Method in class javax.media.protocol.RateRange
Get the current rate.
```

getCurrentState(). Method in class javax.media.TransitionEvent Get the Controller's state at the time this event was generated getDataSource(). Method in interface javax.media.MediaProxy Obtain the new DataSource. getDataSourceList(String). Static method in class javax.media.Manager Build a list of DataSource class names from the protocol prefix-list and a protocol name. getDB(). Method in class javax.media.GainChangeEvent Get the GainControl's new gain value in dB. getDB(). Method in interface javax.media.GainControl Get the current gain set for this object in dB. getDuration(). Method in interface javax.media.Duration Get the duration of the media represented by this object. getDuration(). Method in class javax.media.DurationUpdateEvent Get the duration of the media that this Controller is using. getDuration(). Method in class javax.media.protocol.URLDataSource Returns Duration.DURATION_UNKNOWN. getGainControl(). Method in interface javax.media.Player Obtain the object for controlling this Player's audio gain. getHandlerClassList(String). Static method in class javax.media.Manager Build a list of Handler/CODE> classes from the content-prefix-list and a content name. getLevel(). Method in class javax.media.GainChangeEvent Get the GainControl's new gain value in the level scale. getLevel(). Method in interface javax.media.GainControl Get the current gain set for this object as a value between 0.0 and 1.0 getLocator(). Method in class javax.media.protocol.DataSource Get the MediaLocator that describes this source. getMaximumRate(). Method in class javax.media.protocol.RateRange Get the maximum rate supported by this range. getMediaNanoseconds(). Method in interface javax.media.Clock Get this Clock's current media time in nanoseconds. getMediaTime(). Method in interface javax.media.Clock Get this Clock's current media time. getMediaTime(). Method in class javax.media.MediaTimeSetEvent Get the new media time of the Controller that generated this event. getMediaTime(). Method in class javax.media.StartEvent Get the clock time (media time) when the Controller started. getMediaTime(). Method in class javax.media.StopEvent Get the clock time (media time) that was passed into the constructor. getMessage(). Method in class javax.media.ControllerClosedEvent Obtain the message describing why this event occurred. getMinimumRate(). Method in class javax.media.protocol.RateRange Get the minimum rate supported by this range. getMinimumTransferSize(). Method in interface javax.media.protocol.PushSourceStream Determine the size of the buffer needed for the data transfer.

getMute(). Method in class javax.media.GainChangeEvent Get the GainControl's new mute value. getMute(). Method in interface javax.media.GainControl Get the mute state of the signal associated with this GainControl. getNanoseconds(). Method in class javax.media.Time Get the time value in nanoseconds. getNanoseconds(). Method in interface javax.media.TimeBase Get the current time of the TimeBase specified in nanoseconds. getPreviousState(). Method in class javax.media.TransitionEvent Get the state that the Controller was in before this event occurred. getProgressBarComponent(). Method in interface javax.media.CachingControl Get a Component for displaying the download progress. getProtocol(). Method in class javax.media.MediaLocator Get the beginning of the locator string up to but not including the first colon. getProtocolPrefixList(). Static method in class javax.media.PackageManager Get the current value of the protocol package-prefix list. getRate(). Method in interface javax.media.Clock Get the current temporal scale factor. getRate(). Method in class javax.media.RateChangeEvent Get the new rate of the Controller that generated this event. getRate(). Method in interface javax.media.protocol.RateConfiguration Get the RateRange for this configuration. getRateConfigurations(). Method in interface javax.media.protocol.RateConfigureable Get the rate configurations that this object supports. getRemainder(). Method in class javax.media.MediaLocator Get the MediaLocator string with the protocol removed. getSeconds(). Method in class javax.media.Time Get the time value in seconds. getSource(). Method in class javax.media.ControllerEvent getSource(). Method in class javax.media.GainChangeEvent Get the object that posted this event. getSource(). Method in interface javax.media.MediaEvent getSourceController(). Method in class javax.media.ControllerEvent Get the Controller that posted this event. getSourceGainControl(). Method in class javax.media.GainChangeEvent Get the GainControl that posted this event. getStartLatency(). Method in interface javax.media.Controller Get the Controller's start latency in nanoseconds. getState(). Method in interface javax.media.Controller Get the current state of this Controller. getStopTime(). Method in interface javax.media.Clock Get the last value successfully set by setStopTime.

getStopTime(). Method in class javax.media.StopTimeChangeEvent Get the new stop-time for the Controller that generated this event. getStreams(). Method in class javax.media.protocol.PullDataSource Get the collection of streams that this source manages. getStreams(). Method in class javax.media.protocol.PushDataSource Get the collection of streams that this source manages. getStreams(). Method in interface javax.media.protocol.RateConfiguration Get the streams that will have content at this rate. getStreams(). Method in class javax.media.protocol.URLDataSource Get the collection of streams that this source manages. getSyncTime(). Method in interface javax.media.Clock Get the current media time or the time until this Clock will synchronize to its TimeBase. getSystemTimeBase(). Static method in class javax.media.Manager Get the time-base object for the system. getTargetState(). Method in interface javax.media.Controller Get the current target state of this Controller. getTargetState(). Method in class javax.media.TransitionEvent Get the Controller's target state at the time this event was generated. getTime(). Method in interface javax.media.TimeBase Get the current time of this TimeBase. getTimeBase(). Method in interface javax.media.Clock Get the TimeBase that this Clock is using. getTimeBaseTime(). Method in class javax.media.StartEvent Get the time-base time that started the Controller. getURL(). Method in class javax.media.MediaLocator Get the URL associated with this MediaLocator. getVisualComponent(). Method in interface javax.media.Player Obtain the display Component for this Player.

Ι

IncompatibleSourceException(). Constructor for class
javax.media.IncompatibleSourceException
IncompatibleSourceException(String). Constructor for class
javax.media.IncompatibleSourceException
IncompatibleTimeBaseException(). Constructor for class
javax.media.IncompatibleTimeBaseException
IncompatibleTimeBaseException(String). Constructor for class
javax.media.IncompatibleTimeBaseException
initCheck(). Method in class javax.media.protocol.DataSource
 Check to see if this connection has been initialized with a
 MediaLocator.
InternalErrorEvent(Controller). Constructor for class
javax.media.InternalErrorEvent

InternalErrorEvent(Controller, String). Constructor for class
javax.media.InternalErrorEvent
isDownloading(). Method in interface javax.media.CachingControl
 Check whether or not media is being downloaded.
isExact(). Method in class javax.media.protocol.RateRange
 Determine whether or not the source will maintain a constant
 speed when using this rate.
isRandomAccess(). Method in interface
javax.media.protocol.Positionable
 Find out if this source can be repositioned to any point in the
 stream.
isRandomAccess(). Method in interface javax.media.protocol.Seekable
 Find out if this source can position anywhere in the stream.

L

LATENCY_UNKNOWN. Static variable in interface javax.media.Controller Returned by getStartLatency.

LENGTH_UNKNOWN. Static variable in interface

javax.media.CachingControl

Use to indicate that the CachingControl doesn't know how long the content is.

The definition is: LENGTH_UNKNOWN == Long.MAX_VALUE LENGTH_UNKNOWN. Static variable in interface javax.media.protocol.SourceStream

Μ

components.

```
mapToTimeBase(Time). Method in interface javax.media.Clock
  Get the TimeBase time corresponding to the specified media time.
MediaError(). Constructor for class javax.media.MediaError
MediaErception(). Constructor for class javax.media.MediaException
MediaException(String). Constructor for class
javax.media.MediaException
MediaLocator(String). Constructor for class javax.media.MediaLocator
MediaLocator(URL). Constructor for class javax.media.MediaLocator
MediaLocator(URL). Constructor for class javax.media.MediaLocator
MediaTimeSetEvent(Controller, Time). Constructor for class
javax.media.MediaTimeSetEvent
message. Variable in class javax.media.ControllerClosedEvent
mimeTypeToPackageName(String). Static method in class
javax.media.protocol.ContentDescriptor
Map a MIME content-type to an equivalent string of class-name
```

Ν

nanoseconds. Variable in class javax.media.Time Time is kept to a granularity of nanoseconds. NoDataSourceException(). Constructor for class javax.media.NoDataSourceException NoDataSourceException(String). Constructor for class javax.media.NoDataSourceException NoPlayerException(). Constructor for class javax.media.NoPlayerException NoPlayerException(String). Constructor for class javax.media.NoPlayerException NotPrefetchedError(String). Constructor for class javax.media.NotPrefetchedError NotRealizedError(String). Constructor for class javax.media.NotPrefetchedError

0

ONE_SECOND. Static variable in class javax.media.Time

P

PackageManager(). Constructor for class javax.media.PackageManager prefetch(). Method in interface javax.media.Controller Process as much data as necessary to reduce the Controller's start latency to the shortest possible time. PrefetchCompleteEvent(Controller, int, int, int). Constructor for class javax.media.PrefetchCompleteEvent Prefetched. Static variable in interface javax.media.Controller Returned by getState. Prefetching. Static variable in interface javax.media.Controller Returned by getState. PullDataSource(). Constructor for class javax.media.protocol.PullDataSource PushDataSource(). Constructor for class javax.media.protocol.PushDataSource

R

RateChangeEvent(Controller, float). Constructor for class
javax.media.RateChangeEvent
RateRange(float, float, float, boolean). Constructor for class
javax.media.protocol.RateRange
 Constructor using required values.

```
RateRange(RateRange). Constructor for class
javax.media.protocol.RateRange
   Copy constructor.
read(byte[], int, int). Method in interface
javax.media.protocol.PullSourceStream
   Block and read data from the stream.
read(byte[], int, int). Method in interface
javax.media.protocol.PushSourceStream
   Read from the stream without blocking.
realize(). Method in interface javax.media.Controller
   Construct the media dependent portions of the Controller.
RealizeCompleteEvent(Controller, int, int, int). Constructor for
class javax.media.RealizeCompleteEvent
Realized. Static variable in interface javax.media.Controller
   Returned by getState.
Realizing. Static variable in interface javax.media.Controller
   Returned by getState.
removeController(Controller). Method in interface javax.media.Player
   Stop controlling a Controller.
removeControllerListener(ControllerListener). Method in interface
javax.media.Controller
   Remove the specified listener from this Controller's listener
   list.
removeGainChangeListener(GainChangeListener). Method in interface
javax.media.GainControl
   Remove interest in gain change update events.
RESET. Static variable in interface javax.media.Clock
   Returned by getStopTime if the stop-time is unset.
ResourceUnavailableEvent(Controller). Constructor for class
javax.media.ResourceUnavailableEvent
ResourceUnavailableEvent(Controller, String). Constructor for class
javax.media.ResourceUnavailableEvent
RestartingEvent(Controller, int, int, int, Time). Constructor for
class javax.media.RestartingEvent
RoundDown. Static variable in interface
javax.media.protocol.Positionable
RoundNearest. Static variable in interface
javax.media.protocol.Positionable
RoundUp. Static variable in interface
javax.media.protocol.Positionable
```

S

secondsToNanoseconds(double). Method in class javax.media.Time
Convert seconds to nanoseconds.

seek(long). Method in interface javax.media.protocol.Seekable Seek to the specified point in the stream.

setContentPrefixList(Vector). Static method in class javax.media.PackageManager Set the current value of the content package-prefix list. **setCurrentRate**(float). Method in class javax.media.protocol.RateRange Set the current rate. **setDB**(float). Method in interface javax.media.GainControl Set the gain in decibels. **setLevel**(float). Method in interface javax.media.GainControl Set the gain using a floating point scale with values between 0.0 and 1.0. setLocator(MediaLocator). Method in class javax.media.protocol.DataSource Set the connection source for this DataSource. **setMediaTime**(Time). Method in interface javax.media.Clock Set the Clock's media time. **setMute**(boolean). Method in interface javax.media.GainControl Mute or unmute the signal associated with this GainControl. **setPosition**(Time, int). Method in interface javax.media.protocol.Positionable Set the position to the specified time. setProtocolPrefixList(Vector). Static method in class javax.media.PackageManager Set the protocol package-prefix list. setRate(float). Method in interface javax.media.Clock Set the temporal scale factor. **setRateConfiguration**(RateConfiguration). Method in interface javax.media.protocol.RateConfigureable Set a new RateConfiguration. setSource(DataSource). Method in interface javax.media.MediaHandler Set the media source the MediaHandler should use to obtain content. setStopTime(Time). Method in interface javax.media.Clock Set the media time at which you want the Clock to stop. setTimeBase(TimeBase). Method in interface javax.media.Clock Set the TimeBase for this Clock. **setTransferHandler**(SourceTransferHandler). Method in interface javax.media.protocol.PushSourceStream Register an object to service data transfers to this stream. sources. Variable in class javax.media.protocol.URLDataSource **start**(). Method in class javax.media.protocol.DataSource Initiate data-transfer. start(). Method in interface javax.media.Player Start the Player as soon as possible. start(). Method in class javax.media.protocol.URLDataSource Initiate data-transfer. started. Static variable in interface javax.media.Controller Returned by getState.

StartEvent (Controller, int, int, int, Time, Time). Constructor for class javax.media.StartEvent Construct a new StartEvent. stop(). Method in interface javax.media.Clock Stop the Clock. stop(). Method in class javax.media.protocol.DataSource Stop the data-transfer. **stop**(). Method in class javax.media.protocol.URLDataSource Stops the StopAtTimeEvent(Controller, int, int, int, Time). Constructor for class javax.media.StopAtTimeEvent StopByRequestEvent (Controller, int, int, int, Time). Constructor for class javax.media.StopByRequestEvent StopEvent(Controller, int, int, int, Time). Constructor for class javax.media.StopEvent **StopTimeChangeEvent**(Controller, Time). Constructor for class javax.media.StopTimeChangeEvent StopTimeSetError(String). Constructor for class javax.media.StopTimeSetError syncStart(Time). Method in interface javax.media.Clock Synchronize the current media time to the specified time-base time and start the Clock.

Т

tell (). Method in interface javax.media.protocol.Seekable
Obtain the current point in the stream.
Time (double). Constructor for class javax.media.Time
Construct a time in seconds.
Time(long). Constructor for class javax.media.Time
Construct a time in nanoseconds.
toExternalForm(). Method in class javax.media.MediaLocator
Create a string from the URL argument that can be used to
construct the MediaLocator.
toString(). Method in class javax.media.MediaLocator
Used for printing MediaLocators.
transferData(PushSourceStream). Method in interface
javax.media.protocol.SourceTransferHandler
Transfer new data from a PushSourceStream.
TransitionEvent(Controller, int, int, int). Constructor for class
javax.media.TransitionEvent
Construct a new TransitionEvent.
typeName. Variable in class javax.media.protocol.ContentDescriptor

U

UNKNOWN_CONTENT_NAME. Static variable in class javax.media.Manager Unrealized. Static variable in interface javax.media.Controller Returned by getState. URLDataSource(). Constructor for class javax.media.protocol.URLDataSource Implemented by subclasses. URLDataSource(URL). Constructor for class javax.media.protocol.URLDataSource Construct a URLDataSource directly from a URL.

W

willReadBlock(). Method in interface
javax.media.protocol.PullSourceStream
Find out if data is available now.

package javax.media

Interface Index

- CachingControl
- Clock
- Control
- Controller
- ControllerListener
- Duration
- GainChangeListener
- GainControl
- MediaEvent
- MediaHandler
- MediaProxy
- Player
- TimeBase

Class Index

- CachingControlEvent
- ConnectionErrorEvent
- ControllerClosedEvent
- ControllerErrorEvent
- ControllerEvent
- DataStarvedEvent
- DeallocateEvent
- DurationUpdateEvent
- EndOfMediaEvent
- GainChangeEvent
- InternalErrorEvent
- Manager
- MediaLocator
- MediaTimeSetEvent
- PackageManager
- PrefetchCompleteEvent
- RateChangeEvent
- RealizeCompleteEvent
- ResourceUnavailableEvent
- RestartingEvent
- StartEvent
- StopAtTimeEvent
- StopByRequestEvent

- StopEvent
- StopTimeChangeEvent
- Time
- TransitionEvent

Exception Index

- ClockStoppedException
- IncompatibleSourceException
- IncompatibleTimeBaseException
- MediaException
- NoDataSourceException
- NoPlayerException

Error Index

- ClockStartedError
- MediaError
- NotPrefetchedError
- NotRealizedError
- StopTimeSetError

package javax.media.protocol

Interface Index

- Controls
- Positionable
- PullSourceStream
- PushSourceStream
- RateConfiguration
- RateConfigureable
- Seekable
- SourceStream
- SourceTransferHandler

Class Index

- ContentDescriptor
- DataSource
- PullDataSource
- PushDataSource
- RateRange
- URLDataSource

Interface javax.media.CachingControl

public interface **CachingControl** extends Control

CachingControl is an interface supported by Players that are capable of reporting download progress. Typically, this control is accessed through the Controller.getControls method. A Controller that supports this control will post CachingControlEvents often enough to support the implementation of custom progress GUIs.

Version:

1.18, 97/08/25.

See Also:

Controller, ControllerListener, CachingControlEvent, Player

Variable Index

o LENGTH_UNKNOWN

Use to indicate that the CachingControl doesn't know how long the content is.

The definition is: LENGTH_UNKNOWN == Long.MAX_VALUE

Method Index

o getContentLength()

Get the total number of bytes in the media being downloaded.

o getContentProgress()

Get the total number of bytes of media data that have been downloaded so far.

o getControlComponent()

Get a Component that provides additional download control.

o getProgressBarComponent()

Get a Component for displaying the download progress.

o isDownloading()

Check whether or not media is being downloaded.

Variables

o LENGTH_UNKNOWN

public static final long LENGTH_UNKNOWN

Use to indicate that the CachingControl doesn't know how long the content is.

The definition is: LENGTH_UNKNOWN == Long.MAX_VALUE

Methods

o isDownloading

```
public abstract boolean isDownloading()
```

Check whether or not media is being downloaded.

Returns:

Returns true if media is being downloaded; otherwise returns false..

o getContentLength

public abstract long getContentLength()

Get the total number of bytes in the media being downloaded. Returns LENGTH_UNKNOWN if this information is not available.

Returns:

The media length in bytes, or LENGTH_UNKNOWN.

o getContentProgress

public abstract long getContentProgress()

Get the total number of bytes of media data that have been downloaded so far.

Returns:

The number of bytes downloaded.

o getProgressBarComponent

```
public abstract Component getProgressBarComponent()
```

Get a Component for displaying the download progress.

Returns:

Progress bar GUI.

o getControlComponent

```
public abstract Component getControlComponent()
```

Get a Component that provides additional download control. Returns null if only a progress bar is provided.

Returns:

Download control GUI.

Class javax.media.CachingControlEvent

java.lang.Object
 |
 +----javax.media.ControllerEvent
 |
 +----javax.media.CachingControlEvent

public class **CachingControlEvent** extends ControllerEvent

This event is generated by a Controller that supports the CachingControl interface. It is posted when the caching state changes.

Version: 1.10, 97/08/23. See Also: Controller, ControllerListener, CachingControl

Constructor Index

o **CachingControlEvent**(Controller, CachingControl, long) Construct a CachingControlEvent from the required elements.

Method Index

o getCachingControl()
 Get the CachingControl object that generated the event.
o getContentProgress()
 Get the total number of bytes of media data that have been downloaded so far.

Constructors

o CachingControlEvent

Construct a CachingControlEvent from the required elements.

Methods

o getCachingControl

public CachingControl getCachingControl()

Get the CachingControl object that generated the event.

Returns:

The CachingControl object.

o getContentProgress

public long getContentProgress()

Get the total number of bytes of media data that have been downloaded so far.

Returns:

The number of bytes of media data downloaded.

Interface javax.media.Clock

public interface Clock

The Clock interface is implemented by objects that support the Java Media time model. For example, this interface might be implemented by an object that decodes and renders MPEG movies.

Clock and TimeBase

A Clock contains a TimeBase that provides a source of time, much like a crystal oscillator. The only information that a TimeBase provides is its current time; it does not provide any methods for influencing how time is kept. A Clock defines a transformation on the time that its TimeBase keeps, typically marking time for a particular media stream. The time that a Clock keeps is referred to as the *media time*.

Clock Transform

The transformation that a Clock defines on a TimeBase is defined by three parameters: rate, *media start-time* (mst), and *time-base start-time* (tbst). Given a *time-base time* (tbt), the *media time* (mt) can be calculated using the following transformation:

mt = mst + (tbt - tbst)*rate

The rate is simply a scale factor that is applied to the TimeBase. For example, a rate of 2.0 indicates that the Clock will run at twice the rate of its TimeBase. Similarly, a negative rate indicates that the Clock runs in the opposite direction of its TimeBase.

The *time-base start-time* and the *media start-time* define a common point in time at which the Clock and the TimeBase are synchronized.

Default Time Base

A Clock has a default TimeBase. For many objects that support the Clock interface, the default TimeBase is the system TimeBase. The system TimeBase can be obtained from Manager through the getSystemTimeBase method.

Some Clocks have a TimeBase other than the system TimeBase. For example, an audio renderer that implements the Clock interface might have a TimeBase that represents a hardware clock.

Using a Clock

You can get the TimeBase associated with a Clock by calling the getTimeBase method. To change the TimeBase that a Clock uses, you call the setTimeBase method. These get and set methods can be used together to synchronize different Clocks to the same TimeBase.

For example, an application might want to force a video renderer to sync to the TimeBase of an audio renderer. To do this, the application would call getTimeBase on the audio renderer and then use the value returned to call setTimeBase on the video renderer. This would ensure that the two rendering objects use the same source of time. You can reset a Clock to use its default TimeBase by calling setTimeBase(null).

Some Clocks are incapable of using another TimeBase. If this is the case, an IncompatibleTimeBaseException is thrown when setTimeBase is called.

Clock also provides methods for getting and setting a Clock 's *media time* and rate:

- getMediaTime and setMediaTime
- getRate and setRate

Starting a Clock

Until a Clock 's TimeBase transformation takes effect, the Clock is in the *Stopped* state. Once all three transformation parameters (*media start-time*, *time-base start-time*, and rate) have been provided to the Clock, it enters the *Started* state.

To start a Clock, syncStart is called with the *time-base start-time* as an argument. The new *media start-time* is taken as the current *media time*, and the current rate defines the Clock's rate parameter. When syncStart is called, the Clock and its TimeBase are locked in sync and the Clock is considered to be in the *Started* state.

When a Clock is stopped and then restarted (using syncStart), the *media start-time* for the restarted Clock is the current *media time*. The syncStart method is often used to synchronize two Clocks that share the same TimeBase. When the *time-base start-time* and rate of each clock are set to the same values and each Clock is set with the appropriate *media start-time*, the two Clocks will run in sync.

When syncStart is called with a new *time-base start-time*, the synchronization with the *media time* doesn't occur until the TimeBase reaches the *time-base start-time*. The getMediaTime method returns the untransformed *media time* until the TimeBase reaches the *time-base start-time*.

The getSyncTime method behaves slightly differently. Once syncStart is invoked, getSyncTime always reports the transformed *time-base time*, whether or not the *time-base start-time* has been reached. You can use getSyncTime to determine how much time remains before the *time-base start-time* is reached. When the *time-base start-time* is reached, both getMediaTime and getSyncTime return the same value.

Objects that implement the Clock interface can provide more convenient start methods than syncStart. For example, Player defines start, which should be used instead of syncStart to start a Player.

Stopping a Clock

A *Stopped* Clock is no longer synchronized to its TimeBase. When a Clock is *Stopped*, its *media time* no longer moves in rate-adjusted synchronization with the *time-base time* provided by its TimeBase.

There are two ways to explicitly stop a Clock: you can invoke stop or set a *media stop-time*. When stop is invoked, synchronization with the TimeBase immediately stops. When a *media stop-time* is set, synchronization stops when the *media stop-time* passes.

A Clock's rate affects how its *media stop-time* is interpreted. If its rate is positive, the Clock stops when the *media time* becomes greater than or equal to the stop time. If its rate is negative, the Clock stops when the *media time* becomes less than or equal to the stop time.

If the stop-time is set to a value that the Clock has already passed, the Clock immediately stops.

Once a stop-time is set, it remains in effect until it is changed or cleared. To clear a stop-time, call setStopTime with Clock.RESET. A Clock 's stop-time is cleared automatically when it stops.

If no stop-time is ever set or if the stop-time is cleared, the only way to stop the Clock is to call the stop method.

Clock State

Conceptually, a Clock is always in one of two states: *Started* or *Stopped*. A Clock enters the *Started* state after syncStart has been called and the Clock is mapped to its TimeBase. A Clock returns to the *Stopped* state immediately when the stop method is called or the *media time* passes the stop time.

Certain methods can only be invoked when the Clock is in a particular state. If the Clock is in the wrong state when one of these methods is called, an error or exception is thrown.

Methods Restricted to Started Clocks

The mapToTimeBase method can only be called on a Clock in the *Started* state. If it is invoked on a *Stopped* Clock, a ClockStoppedException is thrown. This is because the Clock is not synchronized to a TimeBase when it is *Stopped*.

Methods Restricted to Stopped Clocks

The following methods can only be called on a Clock in the *Stopped* state. If invoked on a *Started* Clock, these methods throw a ClockStartedError.

- syncStart
- setTimeBase
- setMediaTime
- setRate

Resetting the rate, the *media time*, the time base, or the *time-base start-time* implies a complete remapping between the Clock and its TimeBase and is not allowed on a *Started* Clock.

Methods with Additional Restrictions

A race condition occurs if a new *media stop-time* is set when a Clock is already approaching a previously set *media stop-time*. In this situation, it impossible to guarantee when the Clock will stop. To prevent this race condition, setStopTime can only be set once on a *Started* Clock. A StopTimeSetError is thrown if setStopTime is called and the *media stop-time* has already been set.

There are no restrictions on calling setStopTime on a *Stopped* Clock; the stop time can always be reset if the Clock is *Stopped*.

Version:

1.42, 97/08/25 See Also:

TimeBase, Player

Variable Index

o RESET

Returned by getStopTime if the stop-time is unset.

Method Index

o getMediaNanoseconds() Get this Clock 's current *media time* in nanoseconds. o getMediaTime() Get this Clock 's current media time. o getRate() Get the current temporal scale factor. o getStopTime() Get the last value successfully set by setStopTime. o getSyncTime() Get the current *media time* or the time until this Clock will synchronize to its TimeBase. o getTimeBase() Get the TimeBase that this Clock is using. o **mapToTimeBase**(Time) Get the TimeBase time corresponding to the specified *media time*. o **setMediaTime**(Time) Set the Clock 's media time. o **setRate**(float) Set the temporal scale factor. o **setStopTime**(Time) Set the *media time* at which you want the Clock to stop. o setTimeBase(TimeBase) Set the TimeBase for this Clock. o stop() Stop the Clock. o syncStart(Time) Synchronize the current *media time* to the specified *time-base time* and start the Clock.

Variables

o RESET

public static final Time RESET

Returned by getStopTime if the stop-time is unset.

Methods

o setTimeBase

public abstract void setTimeBase(TimeBase master) throws IncompatibleTimeBaseException

Set the TimeBase for this Clock. This method can only be called on a *Stopped* Clock. A ClockStartedError is thrown if setTimeBase is called on a *Started* Clock.

A Clock has a default TimeBase that is determined by the implementation. To reset a Clock to its default TimeBase, call setTimeBase(null).

Parameters:

master - The new TimeBase or null to reset the Clock to its default TimeBase. **Throws:** IncompatibleTimeBaseException

Thrown if the Clock can't use the specified TimeBase.

o syncStart

public abstract void syncStart(Time at)

Synchronize the current *media time* to the specified *time-base time* and start the Clock. The syncStart method sets the *time-base start-time*, and puts the Clock in the *Started* state. This method can only be called on a *Stopped* Clock. A ClockStartedError is thrown if setTimeBase is called on a *Started* Clock.

Parameters:

at - The time-base time to equate with the current media time.

o stop

public abstract void stop()

Stop the Clock. Calling stop releases the Clock from synchronization with the TimeBase. After this request is issued, the Clock is in the *Stopped* state. If stop is called on a *Stopped* Clock, the request is ignored.

o setStopTime

```
public abstract void setStopTime(Time stopTime)
```

Set the *media time* at which you want the Clock to stop. The Clock will stop when its *media time* passes the stop-time. To clear the stop time, set it to: Clock.RESET.

You can always call setStopTime on a *Stopped* Clock.

On a *Started* Clock, the stop-time can only be set *once*. A StopTimeSetError is thrown if setStopTime is called and the *media stop-time* has already been set.

Parameters:

stopTime - The time at which you want the Clock to stop, in media time.

o getStopTime

public abstract Time getStopTime()

Get the last value successfully set by setStopTime. Returns the constant Clock.RESET if no stop time is set. (Clock.RESET is the default stop time.)

Returns:

The current stop time.

o setMediaTime

public abstract void setMediaTime(Time now)

Set the Clock's *media time*. This method can only be called on a *Stopped* Clock. A ClockStartedError is thrown if setMediaTime is called on a *Started* Clock.

Parameters:

now - The new media time.

o getMediaTime

public abstract Time getMediaTime()

Get this Clock 's current *media time*. A *Started* Clock 's *media time* is based on its TimeBase and rate, as described in *Starting a Clock*.

Returns:

The current media time.

o getMediaNanoseconds

public abstract long getMediaNanoseconds()

Get this Clock's current *media time* in nanoseconds.

Returns:

The current *media time* in nanoseconds.

o getSyncTime

public abstract Time getSyncTime()

Get the current *media time* or the time until this Clock will synchronize to its TimeBase. The getSyncTime method is used by Players and advanced applet writers to synchronize Clocks.

Like getMediaTime, this method returns the Clock's current *media time*, which is based on its TimeBase and rate. However, when syncStart is used to start the Clock, getSyncTime performs a countdown to the time-base start-time, returning the time remaining until the *time-base start-time*. Once the TimeBase reaches the *time-base start-time*, getSyncTime and getMediaTime will return the same value.

o getTimeBase

public abstract TimeBase getTimeBase()

Get the TimeBase that this Clock is using.

o mapToTimeBase

public abstract Time mapToTimeBase(Time t) throws ClockStoppedException

Get the TimeBase time corresponding to the specified *media time*.

Parameters:

t - The *media time* to map from. **Returns:** The *time-base time* in *media-time* coordinates. **Throws:** ClockStoppedException Thrown if mapToTimeBase is called on a *Stopped* Clock.

o getRate

public abstract float getRate()

Get the current temporal scale factor. The scale factor defines the relationship between the Clock's *media time* and its TimeBase.

For example, a rate of 2.0 indicates that *media time* will pass twice as fast as the TimeBase time once the Clock starts. Similarly, a negative rate indicates that the Clock runs in the opposite direction of its TimeBase. All Clocks are guaranteed to support a rate of 1.0, the default rate. Clocks are not required to support any other rate.

o setRate

public abstract float setRate(float factor)

Set the temporal scale factor. The argument *suggests* the scale factor to use.

The setRate method returns the actual rate set by the Clock. Clocks should set their rate as close to the requested value as possible, but are not required to set the rate to the exact value of any argument other than 1.0. A Clock is only guaranteed to set its rate exactly to 1.0.

You can only call this method on a *Stopped* Clock. A ClockStartedError is thrown if setRate is called on a *Started* Clock.

Parameters:

factor - The temporal scale factor (rate) to set. **Returns:** The actual rate set.

Class javax.media.ClockStartedError

public class **ClockStartedError** extends MediaError

ClockStartedError is thrown by a *Started* Clock when a method is invoked that is not legal on a Clock in the *Started* state. For example, this error is thrown if syncStart or setTimeBase is invoked on a *Started* Clock. ClockStartedError is also thrown if addController is invoked on a *Started* Player.

Version:

1.15, 97/08/23.

See Also:

Player, Controller, Clock

Constructor Index

```
o ClockStartedError()
```

Construct a ClockStartedError with no message.

o ClockStartedError(String)

Construct a ClockStartedError that contains the specified reason message.

Constructors

o ClockStartedError

public ClockStartedError(String reason)

Construct a ClockStartedError that contains the specified reason message.

o ClockStartedError

```
public ClockStartedError()
```

Construct a ClockStartedError with no message.

Class javax.media.ClockStoppedException

public class **ClockStoppedException** extends MediaException

A ClockStoppedException is thrown when a method that expects the *Clock* to be *Started* is called on a *Stopped* Clock. For example, this exception is thrown if mapToTimeBase is called on a *Stopped* Clock.

Version:

1.12, 97/08/23

Constructor Index

o ClockStoppedException()
o ClockStoppedException(String)

Constructors

o ClockStoppedException

public ClockStoppedException()

o ClockStoppedException

public ClockStoppedException(String reason)

Class javax.media.ConnectionErrorEvent

public class **ConnectionErrorEvent** extends ControllerErrorEvent

A ConnectionErrorEvent is posted when an error occurs within a DataSource when obtaining data or communicating with a server.

Version:

1.6, 97/08/23

Constructor Index

o ConnectionErrorEvent(Controller)
o ConnectionErrorEvent(Controller, String)

Constructors

o ConnectionErrorEvent

public ConnectionErrorEvent(Controller from)

o ConnectionErrorEvent

Interface javax.media.Control

public interface Control

The base interface for processing Control objects.

Version:

1.13, 97/08/26

Method Index

o getControlComponent()

Get the Component associated with this Control object.

Methods

o getControlComponent

public abstract Component getControlComponent()

Get the Component associated with this Control object. For example, this method might return a slider for volume control or a panel containing radio buttons for CODEC control. The getControlComponent method can return null if there is no GUI control for this Control.

Interface javax.media.Controller

public interface **Controller** extends Clock, Duration

Controller, which extends Clock, provides resource-allocation state information, event generation, and a mechanism for obtaining objects that provide additional control over a Controller.

Controller life-cycle

As a Clock, a Controller is always either *Started* or *Stopped*. However, Controller subdivides Clock's *Stopped* state into five resource-allocation phases: *Unrealized*, *Realizing*, *Realized*, *Prefetching*, and *Prefetched*.

The motivation for these life-cycle states is to provide programmatic control over potentially time-consuming operations. For example, when a Controller is first constructed, it's in the *Unrealized* state. While *Realizing*, the Controller performs the communication necessary to locate all of the resources it needs to function (such as communicating with a server, other controllers, or a file system). The realize method allows an application to initiate this potentially time-consuming process (*Realizing*) at an appropriate time. When a Controller is *Realizing* or *Prefetching*, it will eventually transition to another state, such as *Realized*, *Prefetched*, or even *Unrealized*.

Because a Controller is often in one state on its way to another, its destination or *target* state is an integral part of the Controller life-cycle. You can query a Controller to determine both its current state and its target state.

A Controller typically moves from the *Unrealized* state through *Realizing* to the *Realized* state, then through *Prefetching* to the *Prefetched* state, and finally on to the *Started* state. When a Controller finishes because the end of the media stream is reached, its stop time is reached, or the stop method is invoked, the Controller moves from the *Started* state back to *Prefetched* or possibly back to *Realized*, ready to repeat the cycle.

To use a Controller, you set up parameters to manage its movement through these life-cycle states and then move it through the states using the Controller state transition methods. To keep track of the Controller's current state, you monitor the state transition events that it posts when changing states.

State Transition Methods

A Controller has five methods that are used to induce life-cycle state changes: realize, prefetch, deallocate, syncStart, and stop. To transition a Controller to the *Realized*, *Prefetched*, or *Started* state, you use the corresponding method: realize, prefetch, or syncStart. The deallocate and stop methods can change a requested state transition or trigger a state change.

The forward transition methods (realize, prefetch, and syncStart) are executed asynchronously and return immediately. When the requested operation is complete, the Controller posts a ControllerEvent that indicates that the target state has been reached, stop or deallocate has been invoked, or that an error occurred.

The deallocate, and stop methods can change the target state and induce a transition back to a previous state. For example, calling deallocate on a Controller in the *Prefetching* state will move it back to *Realized*. These methods are synchronous.

State Transition Events

A Controller often moves between states in an asynchronous manner. To facilitate the tracking of a Controller's state, every time its state or target state changes, the Controller is required to post a TransitionEvent that describes its previous state, current state, and new target state. By monitoring the Controller event stream, you can determine exactly what a Controller is doing at any point in time.

When one of the asynchronous forward state transition methods completes, the Controller posts the appropriate TransitionEvent or a ControllerErrorEvent indicating that the Controller is no longer usable. For more information about ControllerEvents, see the *Controller Events section*.

To facilitate simple asynchronous method protocols, a Controller always posts a method completion event when one of the asynchronous forward state transition methods is invoked, even if no state or target state change occurs. For example, if realize is called on a *Prefetching* Controller, a RealizeCompleteEvent is immediately posted, even though the Controller remains in the *Prefetching* state and the target state is still *Prefetched*. The method completion events always report the Controller's previous, current, and target state at the time the event was posted.

Controller States

This section describes the semantics of each of the Controller states.

Unrealized State

A newly instanced Controller starts in the *Unrealized* state. An *Unrealized* Controller knows very little about its internals and does not have enough information to acquire all of the resources it needs to function. In particular, an *Unrealized* Controller does not know enough to properly construct a Clock. Therefore, it is illegal to call the following methods on an *Unrealized* Controller:

- getTimeBase
- setTimeBase
- setMediaTime
- setRate
- setStopTime
- getStartLatency

A NotRealizedError is thrown if any of these methods are called on an *Unrealized* Controller.

Realizing and Realized States

A Controller is *Realized* when it has obtained all of the information necessary for it to acquire the resources it needs to function. A *Realizing* Controller is in the process of identifying the resources that it needs to acquire. *Realizing* can be a resource and time-consuming process. A *Realizing* Controller might have to communicate with a server, read a file, or interact with a set of other objects.

Although a *Realized* Controller does not have to acquire any resources, a *Realized* Controller is likely to have acquired all of the resources it needs except those that imply exclusive use of a scarce system resource, such as an audio device or MPEG decoding hardware.

Normally, a Controller moves from the *Unrealized* state through *Realizing* and on to the *Realized* state. After realize has been invoked on a Controller, the only way it can return to the *Unrealized* state is if deallocate is invoked before *Realizing* completes. Once a Controller reaches the *Realized* state, it never returns to the *Unrealized* state; it remains in one of four states: *Realized*, *Prefetching*, *Prefetched*, or *Started*.

Realize method

The realize method executes asynchronously and completion is signaled by a RealizeCompleteEvent or a ControllerErrorEvent.

Prefetching and Prefetched States

Once *Realized*, a Controller might still need to perform a number of time-consuming tasks before it is ready to be started. For example, it might need to acquire scarce hardware resources, fill buffers with media data, or perform other start-up processing. While performing these tasks, the Controller is in the *Prefetching* state. When finished, it moves into the *Prefetched* state. Over a Controller's lifetime, *Prefetching* might have to recur when certain methods are invoked. For example, calling setMediaTime might cause a Player to be *Prefetched* again before it is *Started*.

Once a Controller is *Prefetched*, it is capable of starting as quickly as is possible for that Controller. *Prefetching* reduces the startup latency of a Controller to the minimum possible value. (The startup latency is the value returned by getStartLatency.)

Typically, a Controller moves from the *Realized* state through *Prefetching* and on to the *Prefetched* state. Once *Prefetched*, a Controller remains *Prefetched* unless deallocate, syncStart or a method that changes its state and increases its startup latency is invoked, such as setMediaTime.

A Started Controller returns to the Prefetched or Realized state when it stops.

Prefetch Method

The prefetch method is asynchronous and its completion is signaled by a PrefetchCompleteEvent or a ControllerErrorEvent. As a convenience, if prefetch is invoked before a Controller has reached the *Realized* state, an implicit realize is invoked by changing the target state to *Prefetched*. Both a RealizeCompleteEvent and a

PrefetchCompleteEvent are posted by the Controller as it transitions to the *Prefetched* state.

If a Controller is *Prefetching* and cannot obtain all of the resources it needs to start, it posts a ResourceUnavailableEvent instead of a PrefetchCompleteEvent. This is a catastrophic error condition from which the Controller cannot recover.

Started State

Once *Prefetched*, a Controller can enter the *Started* state. A *Started* Controller's Clock is running and it is processing data. A Controller returns to the *Prefetched* or *Realized* state when it stops because it has reached its stop time, reached the end of the media, or because the stop method was invoked.

When the Controller moves from the *Prefetched* to the *Started* state, it posts a StartEvent. When it moves from the *Started* state to a stopped state, it posts a StopEvent.

A Controller is a Clock; therefore, syncStart, setTimeBase, setMediaTime, and setRate are illegal when the Controller is in the *Started* state.

syncStart

The only way to start a Controller is to call syncStart.

It is illegal to call syncStart unless the Controller is in the *Prefetched* state. If syncStart is called before the Controller is *Prefetched*, a NotPrefetchedError is thrown. Player defines a start method that relaxes this requirement.

Freeing the Resources Used by a Controller

Deallocate is used to stop a Controller's resource consumption. For example, when Applet.stop is called, deallocate should be called to free the resources that the Controller was using. Deallocate stops any resource-consuming activity and releases any exclusive-use resources that the Controller has acquired. Deallocate executes synchronously; when deallocate returns, the resources have been released.

If the Controller is *Unrealized* or *Realizing*, calling deallocate returns it to the *Unrealized* state. Otherwise, calling deallocate returns a Controller to the *Realized* state. Regardless of the state that a Controller is in, deallocate must relinquish any exclusive-use system resources that it holds; the only way to guarantee that a Controller is not holding resources is to call the deallocate method.

It is illegal to call deallocate on a *Started* Controller. You must stop the Controller before it can relinquish its resources.

When deallocate is called, a Controller posts a special StopEvent, DeallocateEvent.

Controller Events

Controller events asynchronously deliver information about Controller state changes. There are four kinds of notifications: life-cycle transition, method acknowledgement, state notification, and error notification.

To receive events, an object must implement the ControllerListener interface and use the addControllerListener method to register its interest in a Controller's events. All Controller events are posted to each registered listener.

The Controller event mechanism is extensible and some Controllers define events other than the ones described here. For example, the DurationUpdateEvents that a Player posts are ControllerEvents.

TransitionEvent

TransitionEvents are posted when a Controller's current or target state changes. TransitionEvent is subclassed to provide a small set of events that are posted for particular kinds of transitions that merit special interest. The class name of the event indicates either the reason that the event was posted (such as EndOfMediaEvent), or the particular transition that the event represents (such as PrefetchCompleteEvent).

In addition to being posted for state transitions, the method acknowledgement events RealizeCompleteEvent, PrefetchCompleteEvent, StartEvent, DeallocateEvent, and StopByRequestEvent are always posted to signify method completion even if no transition has taken place.

RealizeCompleteEvent

Posted when a Controller moves from *Realizing* to the *Realized* state, or when the realize method is invoked and the Controller is already *Realized*.

PrefetchCompleteEvent

Posted when a Controller moves from *Prefetching* to the *Prefetched* state, or when the prefetch method is invoked and the Controller is already *Prefetched*.

StartEvent

Posted when a Controller moves from *Prefetched* to *Started*.

StopEvent

Posted when a Controller moves backward. For example, when moving from *Prefetched* to *Realized* or from *Started* to *Prefetched*. The *reason* that a stop event occurs is often important; this information is provided through several subclasses of StopEvent. StopAtTimeEvent

Posted when a Controller changes state because it has reached its stop time. StopByRequestEvent

Posted when a Controller changes state because stop is invoked. This event is also posted as an acknowledgement to stop requests.

DeallocateEvent

Posted when the deallocate method is invoked, indicating a possible state change and the loss of exclusive-use resources. The current state is either *Unrealized* or *Realized*. This event doesn't always indicate a state change. For example, it is posted even if deallocate is called on a *Realized* Controller.

EndOfMediaEvent

Posted when a Controller has reached the end of the media. ControllerClosedEvent

When a Controller closes it is no longer usable, and it will post a ControllerClosedEvent. Once this has happened method calls on the Controller have undefined behavior. A Controller will close for one of two reasons. Either the close method was invoked on the Controller, or an error has occurred. If a Controller is closed because the close method was invoked, it posts a ControllerClosedEvent. If an error occurs it posts one of the ControllerErrorEvents.

ControllerErrorEvent

This is the super class of all of the error events that can be posted by a Controller. While this event is rarely posted, you should watch for it when processing other error events--this is how you can detect implementation-specific error events.

When a ControllerErrorEvent is posted, it indicates a catastrophic error from which the Controller cannot recover. There is no recovery mechanism for a Controller once one of these events has been posted.

ResourceUnavailableEvent

This error event is posted during *Prefetching* or *Realizing* to indicate that the operation has failed because a required resource was unavailable.

DataLostErrorEvent

This error event is posted when a Controller has lost data.

InternalErrorEvent

This error event is posted when something goes wrong with the Controller for an implementation-specific reason. This usually indicates that there is a problem with the implementation.

Status Change Events

A small number of status changes occur in a Controller where notification of the change is useful, particularly for updating user interface components. Notification of these changes is provided through three ControllerEvents:

RateChangeEvent

Posted when the rate of a Controller changes.

StopTimeChangeEvent

Posted when the stop time of a Controller changes.

MediaTimeSetEvent

Posted when the media time has been set using the setMediaTime method. This event is *not* periodically posted as media time changes due to normal Controller processing and Clock operation.

Controls

A Control is an object that provides a way to affect some aspect of a Controller's operation in a specific way. The Control interface provides access to a GUI Component that is specific to the particular Control. For example, the GainControl interface provides a way to display a GUI control that allows the user to change the volume.

A Controller makes a collection of Controls available that effect the Controller's behavior. To access these Controls, you use the getControls method, which returns an array of supported Controls. If you know the full class or interface name of the Control you want, you can use getControl.

Since an application using a Controller might not know how to use all of the Controls that a Controller supports, it can make the functionality available to a user by providing access to the Component for the Control.

Version:

1.63, 97/08/28

See Also:

Player, Control, ControllerListener, ControllerEvent, TransitionEvent, RealizeCompleteEvent, PrefetchCompleteEvent, StartEvent, StopEvent, EndOfMediaEvent, ControllerErrorEvent, DataLostErrorEvent, ResourceUnavailableEvent, InternalErrorEvent, RateChangeEvent, MediaTimeSetEvent, ClockStartedError, NotRealizedError

Variable Index

o LATENCY_UNKNOWN Returned by getStartLatency.

o **Prefetched**

Returned by getState.

o Prefetching

Returned by getState.

o **Realized**

Returned by getState.

o Realizing

Returned by getState.

o Started

Returned by getState.

o Unrealized

Returned by getState.

Method Index

o addControllerListener(ControllerListener)

```
Specify a ControllerListener to which this Controller will send events. o \ensuremath{\textbf{close}}()
```

Release all resources and cease all activity.

o deallocate()

Abort the current operation and cease any activity that consumes system resources.

o getControl(String)

Get the Control that supports the class or interface specified.

o getControls()

Get a list of the Control objects that this Controller supports.

o getStartLatency()

Get the Controller's start latency in nanoseconds.

o getState()

Get the current state of this Controller.

o getTargetState()

Get the current target state of this Controller.

o prefetch()

Process as much data as necessary to reduce the Controller's start latency to the shortest possible time.

o realize()

Construct the media dependent portions of the Controller.

o removeControllerListener(ControllerListener)

Remove the specified listener from this Controller's listener list.

Variables

o LATENCY_UNKNOWN

public static final Time LATENCY_UNKNOWN

Returned by getStartLatency.

o Unrealized

public static final int Unrealized

Returned by getState.

o Realizing

public static final int Realizing

Returned by getState.

o Realized

public static final int Realized

Returned by getState.

o Prefetching

public static final int Prefetching

Returned by getState.

o Prefetched

public static final int Prefetched

Returned by getState.

o Started

public static final int Started

Returned by getState.

Methods

o getState

public abstract int getState()

Get the current state of this Controller. The state is an integer constant as defined above.

Note: A race condition can occur between the return of this method and the execution of a state changing method.

Returns:

The Controller's current state.

o getTargetState

```
public abstract int getTargetState()
```

Get the current target state of this Controller. The state is an integer constant as defined above.

Note: A race condition can occur between the return of this method and the execution of a state changing method.

Returns:

The Controller's current target state.

o realize

public abstract void realize()

Construct the media dependent portions of the Controller. This can require examining media data and might take some time to complete.

The realize method puts the Controller into the *Realizing* state and returns immediately. When realize is complete and the Controller is in the *Realized* state, the Controller posts a RealizeCompleteEvent.

o prefetch

public abstract void prefetch()

Process as much data as necessary to reduce the Controller's start latency to the shortest possible time. This typically requires examining media data and takes some time to complete.

The prefetch method puts the Controller into the *Prefetching* state and returns immediately. When *Prefetching* is complete and the Controller is in the *Prefetched* state, the Controller posts a PrefetchCompleteEvent.

o deallocate

Abort the current operation and cease any activity that consumes system resources. If a Controller is not yet *Realized*, it returns to the *Unrealized* state. Otherwise, the Controller returns to the *Realized* state.

It is illegal to call deallocate on a *Started* Controller. A ClockStartedError is thrown if deallocate is called and the Controller is in the *Started* state.

o close

public abstract void close()

Release all resources and cease all activity. The close method indicates that the Controller will no longer be used, and the Controller can shut itself down. A ControllerClosedEvent is posted. Methods invoked on a closed Controller might throw errors.

o getStartLatency

```
public abstract Time getStartLatency()
```

Get the Controller's start latency in nanoseconds. The start latency represents a worst-case estimate of the amount of time it will take to present the first frame of data.

This method is useful for determining how far in advance the syncStart method must be invoked to ensure that media will be rendered at the specified start time.

For a Controller that has a variable start latency, the value returned represents the maximum possible start latency. If you call getStartLatency on a Controller that isn't *Prefetched* and getStartLatency returns LATENCY_UNKNOWN, calling prefetch and then calling getStartLatency again after the Controller posts a PrefetchCompleteEvent might return a more accurate estimate. If getStartLatency still returns LATENCY_UNKNOWN, the start latency is indeterminate and you might not be able to use syncStart to synchronize the Controller with other Controllers.

Note: In most cases, the value returned by getStartLatency will change once the Controller is *Prefetched*.

Returns:

The time it will take before the first frame of media can be presented.

o getControls

public abstract Control[] getControls()

Get a list of the Control objects that this Controller supports. If there are no controls, an array of length zero is returned.

Returns:

A list of Controller Controls.

o getControl

public abstract Control getControl(String forName)

Get the Control that supports the class or interface specified. The full class or interface name should be specified. Null is returned if the Control is not supported.

Returns:

Control for the class or interface name.

o addControllerListener

public abstract void addControllerListener(ControllerListener listener)

Specify a ControllerListener to which this Controller will send events. A Controller can have multiple ControllerListeners.

Parameters:

listener - The listener to which the Controller will post events.

o removeControllerListener

public abstract void removeControllerListener(ControllerListener listener)

Remove the specified listener from this Controller's listener list.

Parameters:

listener - The listener that has been receiving events from this Controller.

Class javax.media.ControllerClosedEvent

java.lang.Object | +----javax.media.ControllerEvent | +----javax.media.ControllerClosedEvent

public class **ControllerClosedEvent** extends ControllerEvent

A ControllerClosedEvent describes an event that is generated when an a Controller is closed. This implies that the Controller is no longer operational.

Version: 1.6, 97/08/23. See Also: Controller, ControllerListener

Variable Index

o message

Constructor Index

o ControllerClosedEvent(Controller)
 Construct a ControllerClosedEvent.
o ControllerClosedEvent(Controller, String)

Method Index

o getMessage() Obtain the message describing why this event occurred.

Variables

o message

protected String message

Constructors

o ControllerClosedEvent

public ControllerClosedEvent(Controller from)

Construct a ControllerClosedEvent.

o ControllerClosedEvent

Methods

o getMessage

```
public String getMessage()
```

Obtain the message describing why this event occurred.

Returns:

Message describing event cause.

Class javax.media.ControllerErrorEvent

```
java.lang.Object
    |
    +----javax.media.ControllerEvent
    |
    +----javax.media.ControllerClosedEvent
    |
    +----javax.media.ControllerErrorEvent
```

public class **ControllerErrorEvent** extends ControllerClosedEvent

A ControllerErrorEvent describes an event that is generated when an error condition occurs that will cause a Controller to cease functioning. Events should only subclass from ControllerErrorEvent if the error being reported will result in catastrophic failure if action is I not taken, or if the Controller has already failed. A ControllerErrorEvent indicates that the Controller is closed.

Version:

```
1.16, 97/08/23
See Also:
Controller, ControllerListener
```

Constructor Index

```
o ControllerErrorEvent(Controller)
o ControllerErrorEvent(Controller, String)
```

Constructors

o ControllerErrorEvent

public ControllerErrorEvent(Controller from)

o ControllerErrorEvent

Class javax.media.ControllerEvent

java.lang.Object | +----javax.media.ControllerEvent

public class **ControllerEvent** extends Object implements MediaEvent

ControllerEvent is the base class for events generated by a Controller. These events are used by ControllerListener.

Java Beans Compatibility

This class is designed to support the Java Beans event model. In order to enable

Version:

```
1.11, 97/08/25
```

See Also: Controller, ControllerListener, MediaEvent

Constructor Index

o ControllerEvent(Controller)

Method Index

```
o getSource()
o getSourceController()
Get the Controller that posted this event.
```

Constructors

o ControllerEvent

public ControllerEvent(Controller from)

Methods

o getSourceController

```
public Controller getSourceController()
```

Get the Controller that posted this event. The returned Controller has at least one active listener. (The addListener method has been called on the Controller).

Returns:

The Controller that posted this event.

o getSource

public Object getSource()

Interface javax.media.ControllerListener

public interface ControllerListener

```
ControllerListener is an interface for handling asynchronous events generated by Controllers.
```

Java Beans Support

If implementations of this interface are going to be used with Java Beans they need to also implement either java.util.EventListener or sunw.util.EventListener.

Version:

1.18, 97/08/25 See Also: Controller

Method Index

o controllerUpdate(ControllerEvent)

This method is called when an event is generated by a Controller that this listener is registered with.

Methods

o controllerUpdate

public abstract void controllerUpdate(ControllerEvent event)

This method is called when an event is generated by a Controller that this listener is registered with.

Parameters:

event - The event generated.

Class javax.media.DataStarvedEvent

public class **DataStarvedEvent** extends StopEvent

DataStarvedEvent indicates that a Controller has lost data or has stopped receiving data altogether. This transitions the Controller into a *Stopped* state.

Version: 1.17, 97/08/23 See Also: Controller, ControllerListener

Constructor Index

o DataStarvedEvent(Controller, int, int, int, Time)

Constructors

o DataStarvedEvent

Class javax.media.DeallocateEvent

public class **DeallocateEvent** extends StopEvent

A DeallocateEvent is posted as an acknowledgement of the invocation of the deallocate method. It implies that the scarce resources associated with this Controller are no longer available and must be reacquired.

A DeallocateEvent can be posted at any time regardless of the Controller's previous or current state. DeallocateEvent is a StopEvent because if the Controller is in the *Started* state when the event is posted, it transitions to one of the *Stopped* states.

Version: 1.11, 97/08/23. See Also: Controller, ControllerListener

Constructor Index

o DeallocateEvent(Controller, int, int, int, Time)

Constructors

o DeallocateEvent

Interface javax.media.Duration

public interface Duration

The Duration interface provides a way to determine the duration of the media being played by a media object. Media objects that expose a media duration implement this interface.

A Controller that supports the Duration interface posts a DurationUpdateEvent whenever its duration changes.

Version: 1.16, 97/08/23 See Also: Controller, DurationUpdateEvent

Variable Index

o DURATION_UNBOUNDED

Returned by getDuration. o **DURATION_UNKNOWN** Returned by getDuration.

Method Index

o **getDuration**() Get the duration of the media represented by this object.

Variables

o DURATION_UNBOUNDED

public static final Time DURATION_UNBOUNDED

Returned by getDuration.

o DURATION_UNKNOWN

public static final Time DURATION_UNKNOWN

Returned by getDuration.

Methods

o getDuration

```
public abstract Time getDuration()
```

Get the duration of the media represented by this object. The value returned is the media's duration when played at the default rate. If the duration can't be determined (for example, the media object is presenting live video) getDuration returns DURATION_UNKNOWN.

Returns:

A Time object representing the duration or DURATION_UNKNOWN.

Class javax.media.DurationUpdateEvent

java.lang.Object | +----javax.media.ControllerEvent | +----javax.media.DurationUpdateEvent

public class **DurationUpdateEvent** extends ControllerEvent

DurationUpdateEvent is posted by a Controller when its duration changes.

Version: 1.10, 97/08/23. See Also: Controller, ControllerListener

Constructor Index

o DurationUpdateEvent(Controller, Time)

Method Index

o getDuration() Get the duration of the media that this Controller is using.

Constructors

o DurationUpdateEvent

Methods

o getDuration

```
public Time getDuration()
```

Get the duration of the media that this Controller is using.

Returns:

The duration of this Controller's media.

Class javax.media.EndOfMediaEvent

public class **EndOfMediaEvent** extends StopEvent

An EndOfMediaEvent indicates that the Controller has reached the end of its media and is stopping.

Version: 1.21, 97/08/23. See Also: Controller, ControllerListener

Constructor Index

o EndOfMediaEvent(Controller, int, int, int, Time)

Constructors

o EndOfMediaEvent

Class javax.media.GainChangeEvent

java.lang.Object | +----javax.media.GainChangeEvent

public class **GainChangeEvent** extends Object implements MediaEvent

A GainChangeEvent is posted by a GainControl when its state has been updated.

Java Beans support

Any implementation of this object is required to be subclassed from either java.util.EventObject or sunw.util.EventObject.

Version:

1.14, 97/08/26 See Also: GainControl, GainChangeListener

Constructor Index

o GainChangeEvent(GainControl, boolean, float, float)

Method Index

o getDB()
 Get the GainControl 's new gain value in dB.
o getLevel()
 Get the GainControl 's new gain value in the level scale.
o getMute()
 Get the GainControl 's new mute value.
o getSource()
 Get the object that posted this event.
o getSourceGainControl()
 Get the GainControl that posted this event.

Constructors

o GainChangeEvent

Methods

o getSource

```
public Object getSource()
```

Get the object that posted this event.

Returns:

The object that posted this event.

o getSourceGainControl

```
public GainControl getSourceGainControl()
```

Get the GainControl that posted this event.

Returns:

The GainControl that posted this event.

o getDB

```
public float getDB()
```

Get the GainControl's new gain value in dB.

Returns:

The GainControl's new gain value, in dB.

o getLevel

```
public float getLevel()
```

Get the GainControl's new gain value in the level scale.

Returns:

The GainControl's new gain, in the level scale.

o getMute

```
public boolean getMute()
```

Get the GainControl's new mute value.

Returns:

The GainControl's new mute value.

Interface javax.media.GainChangeListener

public interface GainChangeListener

GainChangeListener is an interface for handling GainChangeEvents generated by GainControls.

Java Beans support

It is required that any implementation of this object is sub-classed either from java.util.EventListener, or sunw.util.EventListener.

Version:

1.11, 97/08/25. See Also: GainControl, GainChangeEvent

Method Index

o gainChange(GainChangeEvent)

This method is called to deliver a GainChangeEvent when the state of a GainControl changes.

Methods

o gainChange

public abstract void gainChange(GainChangeEvent event)

This method is called to deliver a GainChangeEvent when the state of a GainControl changes.

Parameters:

event - The event generated.

Interface javax.media.GainControl

public interface **GainControl** extends Control

GainControl is an interface for manipulating audio signal gain.

Gain and Gain Measures

Gain is a multiplicative value applied to an audio signal that modifies the amplitude of the signal. This interface allows the gain to be specified in either decibels or using a floating point value that varies between 0.0 and 1.0.

Specifying Gain in Decibels

The decibel scale is valid over all float values. A gain of 0.0 dB implies that the audio signal is neither amplified nor attenuated. Positive values amplify the audio signal, negative values attenuate the audio signal. The relationship between a linear gain multiplier and the gain specified in decibels is:

value = pow(10.0, gainDB/20.0)

Specifying Gain in the Level Scale

The level scale ranges from 0.0 to 1.0, where 0.0 represents a gain that is virtually indistinguishable from silence and 1.0 represents the value that is, in some sense, the maximum gain. In other words, 1.0 represents the highest gain value that produces "useful" results. The mapping for producing a linear multiplicative value is implementation dependent.

Decibel and Level Interactions

The dB and level scales are representations of the same gain value. Calling setLevel will affect subsequent getDB invocations. Level and dB are interrelated in the following ways:

- Level Silence Threshold. After setLevel(0.0), getDB returns the value for which smaller values are not usefully distinguishable from silence. Calling setDB with values equal to or less than this silence threshold causes getLevel to return a value of 0.0.
- Level Maximum Threshold. After setLevel(1.0), getDB returns the value for which larger values are not useful. Calling setDB with values equal to or greater than this threshold causes getLevel to return a value of 1.0.
- The decibel interface is not limited to the thresholds described by the level interface. For example, if you call setDB with a value that is greater than the maximum level threshold and then immediately call getDB, getDB returns the gain that was returned by the setDB, *not* the value that would be returned if you called setLevel(1.0) and then called getDB.
- Both measures increase gain monotonically with increasing measure values.

Defaults

Gain defaults to a value of 0.0 dB. The corresponding level is implementation dependent. Note that for some implementations, the default level might change on a per-instance basis.

Mute

Muting is independent of the gain. If mute is true, no audio signal is produced by this object; if mute is false an audio signal is produced and the gain is applied to the signal.

Gain Change Events

When the state of the GainControl changes, a GainChangeEvent is posted. This event is delivered through an object that implements GainChangeListener and has been registered as a listener with the GainControl using addGainChangeListener.

Version:

1.33, 97/08/23

See Also:

GainChangeEvent, GainChangeListener, Control

Method Index

```
o addGainChangeListener(GainChangeListener)
    Register for gain change update events.
o getDB()
    Get the current gain set for this object in dB.
o getLevel()
    Get the current gain set for this object as a value between 0.0 and 1.0
o getMute()
    Get the mute state of the signal associated with this GainControl.
o removeGainChangeListener(GainChangeListener)
    Remove interest in gain change update events.
o setDB(float)
    Set the gain in decibels.
o setLevel(float)
    Set the gain using a floating point scale with values between 0.0 and 1.0.
o setMute(boolean)
    Mute or unmute the signal associated with this GainControl.
```

Methods

o setMute

public abstract void setMute(boolean mute)

Mute or unmute the signal associated with this GainControl. Calling setMute(true) on an object that is already muted is ignored, as is calling setMute(false) on an object that is not currently muted. Going from a muted to an unmuted state doesn't effect the gain.

Parameters:

mute - Specify true to mute the signal, false to unmute the signal.

o getMute

```
public abstract boolean getMute()
```

Get the mute state of the signal associated with this GainControl.

Returns:

The mute state.

o setDB

public abstract float setDB(float gain)

Set the gain in decibels. Setting the gain to 0.0 (the default) implies that the audio signal is neither amplified nor attenuated. Positive values amplify the audio signal and negative values attenuate the signal.

Parameters:

gain - The new gain in dB.

Returns:

The gain that was actually set.

o getDB

```
public abstract float getDB()
```

Get the current gain set for this object in dB.

Returns:

The gain in dB.

o setLevel

```
public abstract float setLevel(float level)
```

Set the gain using a floating point scale with values between 0.0 and 1.0. 0.0 is silence; 1.0 is the loudest useful level that this GainControl supports.

Parameters:

level - The new gain value specified in the level scale.

Returns:

The level that was actually set.

o getLevel

```
public abstract float getLevel()
```

Get the current gain set for this object as a value between 0.0 and 1.0

Returns:

The gain in the level scale (0.0-1.0).

o addGainChangeListener

public abstract void addGainChangeListener(GainChangeListener listener)

Register for gain change update events. A GainChangeEvent is posted when the state of the GainControl changes.

Parameters:

listener - The object to deliver events to.

o removeGainChangeListener

public abstract void removeGainChangeListener(GainChangeListener listener)

Remove interest in gain change update events.

Parameters:

listener - The object that has been receiving events.

Class javax.media.IncompatibleSourceException

public class **IncompatibleSourceException** extends MediaException

An IncompatibleSourceException is thrown by a MediaHandler when setSource is invoked and the MediaHandler cannot support the DataSource.

Version: 1.2, 97/08/23. See Also: DataSource, MediaHandler, Manager

Constructor Index

```
o IncompatibleSourceException()o IncompatibleSourceException(String)
```

Constructors

o IncompatibleSourceException

public IncompatibleSourceException()

o IncompatibleSourceException

```
public IncompatibleSourceException(String reason)
```

Class javax.media.IncompatibleTimeBaseException

public class **IncompatibleTimeBaseException** extends MediaException

An IncompatibleTimeBaseException is generated when Clock.setTimeBase is invoked using a TimeBase that the Clock cannot support. This happens for certain types of Players that can only be driven by their own internal clocks, such as certain commercial video servers.

Note: A Player might throw this exception when addController is called because of the implied setTimeBase in addController.

Version: 1.9, 97/08/23.

See Also: Clock, Player

Constructor Index

o IncompatibleTimeBaseException()
o IncompatibleTimeBaseException(String)

Constructors

o IncompatibleTimeBaseException

public IncompatibleTimeBaseException()

o IncompatibleTimeBaseException

```
public IncompatibleTimeBaseException(String reason)
```

Class javax.media.InternalErrorEvent

public class **InternalErrorEvent** extends ControllerErrorEvent

An InternalErrorEvent indicates that a Controller failed for implementation-specific reasons. This event indicates that there are problems with the implementation of the Controller.

Version:

1.7, 97/08/23 See Also: Controller, ControllerListener

Constructor Index

```
o InternalErrorEvent(Controller)
o InternalErrorEvent(Controller, String)
```

Constructors

```
o InternalErrorEvent
```

public InternalErrorEvent(Controller from)

o InternalErrorEvent

Class javax.media.Manager

java.lang.Object | +----javax.media.Manager

public final class **Manager** extends Object

Manager is the access point for obtaining system dependent resources such as Players, DataSources, and the system TimeBase.

A Player is an object used to control and render multimedia data that is specific to the content type of the data. A DataSource is an object used to deliver time-based multimedia data that is specific to a delivery protocol. A DataSource provides a Player with media data; a Player must have a DataSource. Manager provides access to a protocol and media independent mechanism for constructing Players and DataSources.

Creating Players and DataSources

Manager will createPlayers from a URL, a MediaLocator or a DataSource. Creating a Player requires the following:

- Obtain the connected DataSource for the specified protocol
- Obtain the Player for the content-type specified by the DataSource
- Attach the DataSource to the Player using the setSource method.

Finding DataSources by Protocol

A MediaLocator defines a protocol for obtaining content. DataSources are identified by the protocol that they support. Manager uses the protocol name to find DataSource classes.

To find a DataSource using a MediaLocator, Manager constructs a list of class names from the protocol package-prefix list and the protocol name obtained from the MediaLocator. For each class name in the constructed list a new DataSource is instanced, the MediaLocator is attached, and the DataSource is connected. If no errors have occurred, the process is considered finished and the connected DataSource is used by Manager in any following operations. If there was an error then the next class name in the list is tried. The exact details of the search algorithm is described in the method documentation below.

Finding Players by Content Type

A Player is a MediaHandler. A MediaHandler is a an object that reads data from a DataSource. There are two types of supported MediaHandler: MediaProxy, and Player.

MediaHandlers are identified by the content type that they support. A DataSource identifies the content type of the data it produces with the getContentType method. Manager uses the content type name to find instances of MediaHandler.

To find a MediaHandler using a content type name, Manager constructs a list of class names from the content package-prefix list and the content type name. For each class name in the constructed list a new MediaHandler is instanced, and the DataSource is attached to the MediaHandler using MediaHandler.setSource.

If the MediaHandler is a Player and the setSource was successful the process is finished and the Player is returned. If the setSource failed, another name in the list is tried.

If the MediaHandler is a MediaProxy then a new DataSource is obtained from the MediaProxy, a new list is created for the content type the DataSource supports and the whole thing is tried again.

If a valid Player, is not found then the whole procedure is repeated is repeated with "unknown" substituted for the content-type name. The "unknown" content type is supported by generic Players that are capable of handling a large variety of media types, often in a platform dependent way.

The detailed creation algorithm is specified in the methods below.

Player Threads

Players render media data asynchronously from the main program flow. This implies that a Player must often manage one or more threads. The threads managed by the Player are not in the thread group of the application that calls createPlayer.

System Time Base

All Players need a TimeBase. Many use a system-wide TimeBase, often based on a time-of-day clock. Manager provides access to the system TimeBase through getSystemTimeBase.

Version:

1.57, 97/08/28.

See Also:

URL, MediaLocator, PackageManager, DataSource, URLDataSource, MediaHandler, Player, MediaProxy, TimeBase

Variable Index

o UNKNOWN_CONTENT_NAME

Method Index

o createDataSource(MediaLocator)

Create a DataSource for the specified media.

```
o createDataSource(URL)
Create a DataSource for the specified media.
o createPlayer(DataSource)
Create a Player for the DataSource.
o createPlayer(MediaLocator)
Create a Player for the specified media.
o createPlayer(URL)
Create a Player for the specified media.
o getDataSourceList(String)
Build a list of DataSource class names from the protocol prefix-list and a protocol name.
o getHandlerClassList(String)
Build a list of Handler/CODE> classes from the content-prefix-list and
a content name.
o getSystemTimeBase()
Get the time-base object for the system.
```

Variables

O UNKNOWN_CONTENT_NAME

```
public static final String UNKNOWN_CONTENT_NAME
```

Methods

o createPlayer

public static Player createPlayer(URL sourceURL) throws IOException, NoPlayerException

Create a Player for the specified media. This creates a MediaLocator from the URL and then calls createPlayer.

Parameters:

sourceURL - The URL that describes the media data.
Returns:
 A new Player.
Throws: NoPlayerException
 Thrown if no Player can be found.
Throws: IOException
 Thrown if there was a problem connecting with the source.

o createPlayer

public static Player createPlayer(MediaLocator sourceLocator) throws IOException, NoPlayerException

Create a Player for the specified media.

The algorithm for creating a Player from a MediaLocator is:

- 1. Get the protocol from the MediaLocator.
- 2. Get a list of DataSource classes that support the protocol, using the protocol package-prefix-list.
- 3. For each source class in the list:
 - 1. Instantiate a new DataSource,

- 2. Call the connect method to connect the source.
- Get the media content-type-name (using getContentType) from the source.
- Get a list of MediaHandler classes that support the media-content-type-name, using the content package-prefix-list.
- 5. For each MediaHandler class in the list:
 - 1. Instantiate a new MediaHandler.
 - Attach the source to the MediaHandler by calling MediaHandler.setSource.
 - 3. If there are no failures, determine the type of the MediaHandler; otherwise try the next MediaHandler in the list.
 - 4. If the MediaHandler is a Player, return the new Player.
 - 5. If the MediaHandler is a MediaProxy, obtain a new DataSource from the MediaProxy, obtain the list of MediaHandlers that support the new DataSource, and continue searching the new list.
- 6. If no MediaHandler is found for this source, try the next source in the list.
- 4. If no Player is found after trying all of the sources, reuse the source list.
 - This time, for each source class in the list:
 - 1. Instantiate the source.
 - 2. Call the connect method to connect to the source.
 - 3. Use the content package-prefix-list to create a list of MediaHandler classes that support the "unknown" content-type-name.
 - 4. For each MediaHandler class in the list, search for a Player as in the previous search.
 - 1. If no Player is found after trying all of the sources, a NoPlayerException is thrown.

Parameters:

sourceLocator - A MediaLocator that describes the media content.

Returns:

A Player for the media described by the source.

Throws: NoPlayerException

Thrown if no Player can be found.

Throws: IOException

Thrown if there was a problem connecting with the source.

o createPlayer

public static Player createPlayer(DataSource source) throws IOException, NoPlayerException

Create a Player for the DataSource.

The algorithm for creating a Player from a DataSource is:

- 1. Get the media content-type-name from the source by calling getContentType.
- 2. Use the content package-prefix-list to get a list of Player classes that support the media content-type name.
- 3. For each Player class in the list:
 - 1. Instantiate a new Player.
 - 2. Attach the source to the Player by calling setSource on the Player.

- 3. If there are no failures, return the new Player; otherwise, try the next Player in the list.
- 4. If no Player is found for this source:
 - 1. Use the content package-prefix-list to create a list of Player classes that support the "unknown" content-type-name.
 - 2. For each Player class in the list:
 - 1. Instantiate a new Player.
 - 2. Attach the source to the Player by calling setSource on the Player.
 - 3. If there are no failures, return the new Player; otherwise, try the next Player in the list.
- 5. If no Player can be created, a NoPlayerException is thrown.

Parameters:

DataSource - The DataSource that describes the media content.

Returns:

A new Player. **Throws:** NoPlayerException Thrown if a Player can't be created. **Throws:** IOException Thrown if there was a problem connecting with the source.

o createDataSource

public static DataSource createDataSource(URL sourceURL) throws IOException, NoDataSourceException

Create a DataSource for the specified media.

Parameters:

sourceURL - The URL that describes the media data. **Returns:** A new DataSource for the media. **Throws:** NoDataSourceException Thrown if no DataSource can be found. **Throws:** IOException Thrown if there was a problem connecting with the source. o **createDataSource**

public static DataSource createDataSource(MediaLocator sourceLocator) throws IOException, NoDataSourceException

Create a DataSource for the specified media.

Returns a data source for the protocol specified by the MediaLocator. The returned data source is *connected*; DataSource.connect has been invoked.

The algorithm for creating a DataSource from a MediaLocator is:

- 1. Get the protocol from the MediaLocator.
- 2. Use the protocol package-prefix list to get a list of DataSource classes that support the protocol.
- 3. For each source class in the list:
 - 1. Instantiate a new DataSource.
 - 2. Call connect to connect the source.
 - 3. If there are no errors, return the connected source; otherwise, try the next source in the list.

- 4. If no source has been found, obtain a URL from the MediaLocator and use it to create a URLDataSource
- 5. If no source can be found, a NoDataSourceException is thrown.

Parameters:

sourceLocator - The source protocol for the media data.

Returns:

A connected DataSource. **Throws:** NoDataSourceException Thrown if no DataSource can be found. **Throws:** IOException Thrown if there was a problem connecting with the source. o getSystemTimeBase

o getsystem i meduse

public static TimeBase getSystemTimeBase()

Get the time-base object for the system.

Returns:

The system time base.

o getDataSourceList

public static Vector getDataSourceList(String protocolName)

Build a list of DataSource class names from the protocol prefix-list and a protocol name.

The first name in the list will always be:

media.protocol.<protocol>DataSource

Each additional name looks like:

<protocol-prefix>.media.protocol.<protocol>.DataSource

for every <protocol-prefix> in the protocol-prefix-list.

Parameters:

protocol - The name of the protocol the source must support.

Returns:

A vector of strings, where each string is a Player class-name.

o getHandlerClassList

public static Vector getHandlerClassList(String contentName)

Build a list of Handler/CODE> classes from the content-prefix-list and a content name.

The first name in the list will always be:

media.content.<contentType>.Handler

Each additional name looks like:

<content-prefix>.media.content.<contentName>.Player

for every <content-prefix> in the content-prefix-list.

Parameters:

contentName - The content type to use in the class name.
Returns:

A vector of strings where each one is a Player class-name.

Class javax.media.MediaError

public class **MediaError** extends Error

A MediaError indicates an error condition that occurred through incorrect usage of the API. You should not check for MediaErrors.

Version: 1.11, 97/08/23.

Constructor Index

o MediaError()
o MediaError(String)

Constructors

o MediaError

public MediaError()

o MediaError

public MediaError(String reason)

Interface javax.media.MediaEvent

public interface MediaEvent

MediaEvent is the base interface for events supported by the media framework.

Java Beans support

In order to support the Java Beans event model an implementation of MediaEvent is required to sub-class java.util.EventObject. If an implementation is designed to support the 1.0.2 JDK then it may alternatively sub-class sunw.util.EventObject to provide the support appropriate support. Any class that subclasses MediaEvent must resolve to either java.util.EventObject or sunw.util.EventObject.

Version: 1.3, 97/08/25. See Also: ControllerEvent, GainChangeEvent

Method Index

o getSource()

Methods

o getSource

```
public abstract Object getSource()
```

Class javax.media.MediaException

public class **MediaException** extends Exception

A MediaException indicates an unexpected error condition in a JavaMedia method.

Version:

1.9, 97/08/28

Constructor Index

o MediaException()
o MediaException(String)

Constructors

o MediaException

```
public MediaException()
```

o MediaException

```
public MediaException(String reason)
```

Interface javax.media.MediaHandler

public interface MediaHandler

MediaHandler is the base interface for objects that read and manage media content delivered from a DataSource.

There are currently two supported types of MediaHandler: Player and MediaProxy.

Version:

1.4, 97/08/23.

See Also:

Player, MediaProxy

Method Index

o **setSource**(DataSource) Set the media source the MediaHandler should use to obtain content.

Methods

o setSource

public abstract void setSource(DataSource source) throws IOException, IncompatibleSourceException

Set the media source the MediaHandler should use to obtain content.

Parameters: source - The DataSource used by this MediaHandler. Throws: IOException Thrown if there is an error using the DataSource Throws: IncompatibleSourceException Thrown if this MediaHandler cannot make use of the DataSource.

Class javax.media.MediaLocator

java.lang.Object | +----javax.media.MediaLocator

public class **MediaLocator** extends Object

MediaLocator describes the location of media content. MediaLocator is closely related to URL. URLs can be obtained from MediaLocators, and MediaLocators can be constructed from URL. Unlike a URL, a MediaLocator can be instanced without a URLStreamHandler installed on the System.

Version: 1.8, 97/08/25. See Also: URL, URLStreamHandler

Constructor Index

o MediaLocator(String)
o MediaLocator(URL)

Method Index

o getProtocol()

Get the beginning of the locator string up to but not including the first colon.

o getRemainder()

Get the MediaLocator string with the protocol removed.

o getURL()

Get the URL associated with this MediaLocator.

o toExternalForm()

Create a string from the URL argument that can be used to construct the MediaLocator.

o toString()

Used for printing MediaLocators.

Constructors

o MediaLocator

public MediaLocator(URL url)

Parameters:

url - The URL to construct this media locator from.

o MediaLocator

public MediaLocator(String locatorString)

Methods

o getURL

```
public URL getURL() throws MalformedURLException
```

Get the URL associated with this MediaLocator.

o getProtocol

```
public String getProtocol()
```

Get the beginning of the locator string up to but not including the first colon.

Returns:

The protocol for this MediaLocator.

o getRemainder

```
public String getRemainder()
```

Get the MediaLocator string with the protocol removed.

Returns:

The argument string.

o toString

```
public String toString()
```

Used for printing MediaLocators.

Returns:

A string for printing MediaLocators.

Overrides:

toString in class Object

o toExternalForm

public String toExternalForm()

Create a string from the URL argument that can be used to construct the MediaLocator.

Returns:

A string for the MediaLocator.

Interface javax.media.MediaProxy

public interface **MediaProxy** extends MediaHandler

MediaProxy is a MediaHandler which processes content from one DataSource, to produce another DataSource.

Typically, a MediaProxy reads a text configuration file that contains all of the information needed to make a connection to a server and obtain media data. To produce a Player from a MediaLocator referencing the configuration file, Manger:

- constructs a DataSource for the protocol described by the MediaLocator
- constructs a MediaProxy to read the configuration file using the content-type of the DataSource
- obtains a new DataSource from the MediaProxy
- constructs the Player using the content-type of the new DataSource

Version:

1.10, 97/08/25.

See Also:

Manager

Method Index

o getDataSource()

Obtain the new DataSource.

Methods

o getDataSource

public abstract DataSource getDataSource() throws IOException, NoDataSourceException

Obtain the new DataSource. The DataSource is already connected.

Returns:

the new DataSource for this content. **Throws:** IOException Thrown when if there are IO problems in reading the the original or new DataSource. **Throws:** NoDataSourceException Thrown if this proxy can't produce a DataSource.

Class javax.media.MediaTimeSetEvent

public class **MediaTimeSetEvent** extends ControllerEvent

A MediaTimeSetEvent is posted by a Controller when its media-time has been set with the setMediaTime method.

Version: 1.13, MediaTimeSetEvent.java. See Also: Controller, ControllerListener

Constructor Index

o MediaTimeSetEvent(Controller, Time)

Method Index

o getMediaTime()

Get the new media time of the Controller that generated this event.

Constructors

o MediaTimeSetEvent

Methods

o getMediaTime

```
public Time getMediaTime()
```

Get the new media time of the Controller that generated this event.

Returns:

The Controller's new media time.

Class javax.media.NoDataSourceException

public class **NoDataSourceException** extends MediaException

A NoDataSourceException is thrown when a DataSource can't be found for a particular URL or MediaLocator.

Version:

1.8, 97/08/23.

Constructor Index

o NoDataSourceException()
o NoDataSourceException(String)

Constructors

o NoDataSourceException

public NoDataSourceException()

o NoDataSourceException

public NoDataSourceException(String reason)

Class javax.media.NoPlayerException

public class **NoPlayerException** extends MediaException

A NoPlayerException is thrown when a PlayerFactory can't find a Player for a particular URL or MediaLocator.

Version:

1.8, 97/08/23.

Constructor Index

o NoPlayerException()
o NoPlayerException(String)

Constructors

o NoPlayerException

public NoPlayerException()

o NoPlayerException

```
public NoPlayerException(String reason)
```

Class javax.media.NotPrefetchedError

public class **NotPrefetchedError** extends MediaError

NotPrefetchedError is thrown when a method that requires a Controller to be in the *Prefetched* state is called and the Controller has not been *Prefetched*.

This typically happens when syncStart is invoked on a *Stopped* Controller that hasn't been *Prefetched*.

Version: 1.12, 97/08/23.

See Also: Controller

Constructor Index

o NotPrefetchedError(String)

Constructors

o NotPrefetchedError

public NotPrefetchedError(String reason)

Class javax.media.NotRealizedError

public class **NotRealizedError** extends MediaError

NotRealizedError is thrown when a method that requires a Controller to be in the *Realized* state is called and the Controller is not *Realized*.

For example, this can happen when getComponents is called on an Unrealized Player.

Version:

1.8, 97/08/23. See Also: Controller, Player

Constructor Index

o NotRealizedError(String)

Constructors

o NotRealizedError

```
public NotRealizedError(String reason)
```

Class javax.media.PackageManager

java.lang.Object | +----javax.media.PackageManager

public class **PackageManager** extends Object

A PackageManager maintains a persistent store of package-prefix lists. A package prefix specifies the prefix for a complete class name. A factory uses a package-prefix list to find a class that might belong to any of the packages that are referenced in the prefix list.

The Manager uses package-prefix lists to find protocol handlers and content handlers for time-based media.

The current version of a package-prefix list is obtained with the get<package-prefix>List method. This method returns the prefix list in use; any changes to the list take effect immediately. Unless it is made persistent with commit<package-prefix>List, a package-prefix list is only valid while the Manager is referenced. The commit<package-prefix>List method ensures that any changes made to a package-prefix list are still visible the next time that the Manager is referenced.

Version: 1.11, 97/08/23. See Also: Manager

Constructor Index

o PackageManager()

Method Index

 o commitContentPrefixList() Make changes to the content prefix-list persistent.
 o commitProtocolPrefixList() Make changes to the protocol package-prefix list persistent.
 o getContentPrefixList() Get the current value of the content package-prefix list.
 o getProtocolPrefixList()

Get the current value of the protocol package-prefix list.

o setContentPrefixList(Vector)

Set the current value of the content package-prefix list.

o **setProtocolPrefixList**(Vector) Set the protocol package-prefix list.

Constructors

o PackageManager

public PackageManager()

Methods

o getProtocolPrefixList

public static Vector getProtocolPrefixList()

Get the current value of the protocol package-prefix list.

Returns:

The protocol package-prefix list.

o setProtocolPrefixList

public static void setProtocolPrefixList(Vector list)

Set the protocol package-prefix list. This is required for changes to take effect.

Parameters:

list - The new package-prefix list to use.

o commitProtocolPrefixList

```
public static void commitProtocolPrefixList()
```

Make changes to the protocol package-prefix list persistent.

This method throws a SecurityException if the calling thread does not have access to system properties.

o getContentPrefixList

```
public static Vector getContentPrefixList()
```

Get the current value of the content package-prefix list. Any changes made to this list take effect immediately.

Returns:

The content package-prefix list.

o setContentPrefixList

```
public static void setContentPrefixList(Vector list)
```

Set the current value of the content package-prefix list. This is required for changes to take effect.

Parameters:

list - The content package-prefix list to set.

o commitContentPrefixList

```
public static void commitContentPrefixList()
```

Make changes to the content prefix-list persistent.

This method throws a SecurityException if the calling thread does not have access to system properties.

Interface javax.media.Player

public interface **Player** extends MediaHandler, Controller, Duration

Player is a MediaHandler for rendering and controlling time based media data. Player extends both the Controller and Duration interfaces Player provides methods for obtaining AWT components, media processing controls, and a way to manage other Controllers.

How a Player Differs from a Controller

Player relaxes some restrictions that a Controller imposes on what methods can be called on a *Started*, *Stopped*, or *Unrealized* Controller. It also provides a way to manage groups of Controllers.

Methods Restricted to Stopped Players

The following methods can only be called on a Player in one of the *Stopped* states. If they are invoked on a *Started* Player, a ClockStartedError is thrown.

- setTimeBase
- syncStart
- deallocate
- addController
- removeController

Methods Allowed on Started Players

Unlike a Controller, the following methods are *legal* on a Player in the *Started* state:

- setMediaTime
- setRate

Invoking these methods on a *Started* Player might initiate significant and time-consuming processing, depending on the location and type of media being processed. These methods might also cause the state of the Player to change. If this happens, the appropriate TransitionEvents are posted by the Player when its state changes.

For example, a Player might have to enter the *Prefetching* state to process a setMediaTime invocation. In this case, the Player posts a RestartingEvent, a PrefetchCompleteEvent, and a StartEvent as it moves from the *Started* state to *Prefetching*, back to *Prefetched*, and finally back to the *Started* state.

Methods that are Illegal on Unrealized Players

As with Controller, it is illegal to call the following methods on an Unrealized Player:

- getTimeBase
- setTimeBase
- setMediaTime
- setRate
- setStopTime
- getStartLatency

It is also illegal to call the following Player methods on an *Unrealized* Player:

- getVisualComponent
- getControlPanelComponent
- getGainControl
- addController
- removeController

The Player throws a NotRealizedError if any of these methods are called while the Player is in the *Unrealized* state.

Start Method

As a convenience, Player provides a start method that can be invoked before a Player is *Prefetched*. This method attempts to transition the Player to the *Started* state from whatever state it's currently in. For example, if the Player is *Unrealized*, start implicitly calls realize, prefetch, and Clock.syncStart. The appropriate TransitionEvents are posted as the Player moves through each state on its way to *Started*.

RestartingEvent

If setMediaTime or setRate cause a perceptible delay in the presentation of the media, the Player posts a RestartingEvent and transitions to the *Prefetching* state. The previous state and target state of a RestartingEvent is always *Started*. RestartingEvent is a subclass of StopEvent.

DurationUpdateEvent

Because a Player cannot always know the duration of the media it is playing, the Duration interface defines that getDuration returns Duration.DURATION_UNKNOWN until the duration can be determined. A DurationUpdateEvent is generated when the Player can determine its duration or the if its duration changes, which can happen at any time. When the end of the media is reached, the duration should be known.

Managing other Controllers

In some situations, an application might want to use a single Player to control other Players or Controllers. A single controlling Player can be used to invoke start, stop, setMediaTime, and other methods on the entire group. The controlling Player manages all of the state transitions and event posting.

It is also possible to construct a simple Controller to update animations, report on media time-line progress, or provide other timing-related functions. Such Controllers can operate in sync with a controlling Player.

Adding a Controller

To have a Player assume control over a Controller, use the addController method. A Controller can only be added to a *Stopped* Player. If addController is called on a *Started* Player, a ClockStartedError is thrown. An *Unrealized* Controller cannot be added to a Player; a NotRealizedError is thrown if the Controller is *Unrealized*.

Once a Controller has been added, the Player:

- Invokes setTimeBase on the Controller with the Player's TimeBase. If this fails, addController throws an IncompatibleTimeBaseException.
- Synchronizes the Controller with the Player using setMediaTime, setStopTime, and setRate.
- Takes the added Controller's latency into account when computing the Player's start latency. When getStartLatency is called, the Player returns the greater of: its latency before the Controller was added and the latency of the added Controller.
- Takes the added Controller's duration into account when computing the Player's duration. When getDuration is called, the Player returns the greater of: its duration before the Controller was added and the duration of the added Controller. If either of these values is DURATION_UNKNOWN, getDuration returns DURATION_UNKNOWN. If either of these values is DURATION_UNBOUNDED getDuration returns DURATION_UNBOUNDED.
- Adds itself as a ControllerListener for the added Controller so that it can manage the events that the Controller generates. (See the Events section below for more information.)
- Invokes control methods on the added Controller in response to methods invoked on the Player. The methods that affect managed Controllers are discussed below.

Once a Controller has been added to a Player, methods should only be called on the Controller through the managing Player. It is not defined how the Controller or Player will behave if methods are called directly on an added Controller. You cannot place a controlling Player under the control of a Player that it is managing; the resulting behavior is undefined.

When a Controller is added to a Player, the Player does not transition the added Controller to new state, nor does the Player transition itself forward. The Player either transitions back to the *realized* state if the added Controller is *realized* or *prefetching* or it stays in the *prefetched* state if the both the Player and the added Controller are in the *prefetched* state. If the Player makes a state transition as a result of adding a Controller the Player posts a TransitionEvent.

Removing a Controller

To stop a Player from managing another Controller, call removeController. The managing Player must be *Stopped* before removeController can be called. A ClockStartedError is thrown if removeController is called on a *Started* Player.

When a Controller is removed from a Player's control, the Player:

- Resets the Controller's TimeBase to its default.
- Recalculates its duration and posts a DurationUpdateEvent if the Player's duration is different without the Controller added.
- Recalculates its start latency.

Setting the Media Time and Rate of a Managing Player

When you call setMediaTime on a Player that's managing other Controllers, its actions differ depending on whether or not the Player is *Started*. If the Player is not *Started*, it simply invokes setMediaTime on all of the Controllers it's managing.

If the Player is *Started*, it posts a RestartingEvent and performs the following tasks for each managed Controller:

- Invokes stop on the Controller.
- Invokes setMediaTime on the Controller.
- Invokes prefetch on the Controller.
- Waits for a PrefetchCompleteEvent from the Controller.
- Invokes syncStart on the Controller

The same is true when setRate is called on a managing Player. The Player attempts to set the specified rate on all managed Controllers, stopping and restarting the Controllers if necessary. If some of the Controllers do not support the requested rate, the Player returns the rate that was actually set. All Controllers are guaranteed to have been successfully set to the rate returned.

Starting a Managing Player

When you call start on a managing Player, all of the Controllers managed by the Player are transitioned to the *Prefetched* state. When the Controllers are *Prefetched*, the managing Player calls syncStart with a time consistent with the latencies of each of the managed Controllers.

Calling realize, prefetch, stop, or deallocate on a Managing Player

When you call realize, prefetch, stop, or deallocate on a managing Player, the Player calls that method on all of the Controllers that it is managing. The Player moves from one state to the next when all of its Controllers have reached that state. For example, a Player in the *Prefetching* state does not transition into the *Prefetched* state until all of its managed Controllers are *Prefetched*. The Player posts TransitionEvents normally as it changes state.

Calling syncStart or setStopTime on a Managing Player

When you call syncStart or setStopTime on a managing Player, the Player calls that method on all of the Controllers that it is managing. (The Player must be in the correct state or an error is thrown. For example, the Player must be *Prefetched* before you can call syncStart.)

Setting the Time Base of a Managing Player

When setTimeBase is called on a managing Player, the Player calls setTimeBase on all of the Controllers it's managing. If setTimeBase fails on any of the Controllers, an IncompatibleTimeBaseException is thrown and the TimeBase last used is restored for all of the Controllers.

Getting the Duration of a Managing Player

Calling getDuration on a managing Player returns the maximum duration of all of the added Controllers and the managing Player. If the Player or any Controller has not resolved its duration, getDuration returns Duration.DURATION_UNKNOWN.

Closing a Managing Player

When close is called on a managing Player all managed Controllers are closed as well.

Events

Most events posted by a managed Controller are filtered by the managing Player. Certain events are sent directly from the Controller through the Player and to the listeners registered with the Player.

To handle the events that a managed Controller can generate, the Player registers a listener with the Controller when it is added. Other listeners that are registered with the Controller must be careful not to invoke methods on the Controller while it is being managed by the Player. Calling a control method on a managed Controller directly will produce unpredictable results.

When a Controller is removed from the Player's list of managed Controllers, the Player removes itself from the Controller's listener list.

Transition Events

A managing Player posts TransitionEvents normally as it moves between states, but the managed Controllers affect when the Player changes state. In general, a Player does not post a transition event until all of its managed Controllers have posted the event.

Status Change Events

The managing Player collects the RateChangeEvents, StopTimeChangeEvents, and MediaTimeSetEvents posted by its managed Controllers and posts a single event for the group.

DurationUpdateEvent

A Player posts a DurationUpdateEvent when it determines its duration or its duration changes. A managing Player's duration might change if a managed Controller updates or discovers its duration. In general, if a managed Controller posts a DurationUpdateEvent and the new duration changes the managing Player's duration, the Player posts a DurationUpdateEvent

CachingControlEvent

A managing Player reposts CachingControlEvents received from a Players that it manages, but otherwise ignores the events.

ControllerErrorEvents

A managing Player immediately reposts any ControllerErrorEvent received from a Controller that it is managing. After a ControllerErrorEvent has been received from a managed Controller, a managing Player no longer invokes any methods on the managed Controller; the managed Controller is ignored from that point on.

Version:

1.75, 97/08/25

See Also:

Manager, GainControl, Clock, TransitionEvent, RestartingEvent, DurationUpdateEvent, Component

Method Index

```
o addController(Controller)
```

Assume control of another Controller.

o getControlPanelComponent()

Obtain the Component that provides the default user interface for controlling this Player.

o getGainControl()

Obtain the object for controlling this Player's audio gain.

o getVisualComponent()

Obtain the display Component for this Player.

o removeController(Controller)

Stop controlling a Controller.

o start()

Start the Player as soon as possible.

Methods

o getVisualComponent

```
public abstract Component getVisualComponent()
```

Obtain the display Component for this Player. The display Component is where visual media is rendered. If this Player has no visual component, getVisualComponent returns null. For example, getVisualComponent might return null if the Player only plays audio.

Returns:

The media display Component for this Player.

o getGainControl

public abstract GainControl getGainControl()

Obtain the object for controlling this Player's audio gain. If this player does not have a GainControl, getGainControl returns null. For example, getGainControl might return null if the Player does not play audio data.

Returns:

The GainControl object for this Player.

o getControlPanelComponent

```
public abstract Component getControlPanelComponent()
```

Obtain the Component that provides the default user interface for controlling this Player. If this Player has no default control panel, getControlPanelComponent returns null.

Returns:

The default control panel GUI for this Player.

o start

```
public abstract void start()
```

Start the Player as soon as possible. The start method attempts to transition the Player to the *Started* state. If the Player has not been *Realized* or *Prefetched*, start automatically performs those actions. The appropriate events are posted as the Player moves through each state.

o addController

public abstract void addController(Controller newController) throws IncompatibleTimeBaseException

Assume control of another Controller.

Parameters:

newController - The Controller to be managed. **Throws:** IncompatibleTimeBaseException Thrown if the added Controller cannot take this * Player's TimeBase.

o removeController

public abstract void removeController(Controller oldController)

Stop controlling a Controller.

Parameters:

oldController - The Controller to stop managing.

Class javax.media.PrefetchCompleteEvent

public class **PrefetchCompleteEvent** extends TransitionEvent

A PrefetchCompleteEvent is posted when a Controller finishes *Prefetching*. This occurs when a Controller moves from the *Prefetching* state to the *Prefetched* state, or as an acknowledgement that the prefetch method was called and the Controller is already *Prefetched*.

Version:

1.20, 97/08/23. **See Also:**

Controller, ControllerListener

Constructor Index

o PrefetchCompleteEvent(Controller, int, int, int)

Constructors

o PrefetchCompleteEvent

Class javax.media.RateChangeEvent

java.lang.Object
 |
 +----javax.media.ControllerEvent
 |
 +----javax.media.RateChangeEvent

public class **RateChangeEvent** extends ControllerEvent

A RateChangeEvent is a ControllerEvent that is posted when a Controller's rate changes.

Version: 1.11, 97/08/23. See Also: Controller, ControllerListener

Constructor Index

o RateChangeEvent(Controller, float)

Method Index

```
o getRate()
```

Get the new rate of the Controller that generated this event.

Constructors

o RateChangeEvent

Methods

o getRate

```
public float getRate()
```

Get the new rate of the Controller that generated this event.

Returns:

The Controller's new rate.

Class javax.media.RealizeCompleteEvent

public class **RealizeCompleteEvent** extends TransitionEvent

A RealizeCompleteEvent is posted when a Controller finishes *Realizing*. This occurs when a Controller moves from the *Realizing* state to the *Realized* state, or as an acknowledgement that the realize method was called and the Controller is already *Realized*.

Version: 1.14, 97/08/23 See Also: Controller, ControllerListener

Constructor Index

o RealizeCompleteEvent(Controller, int, int, int)

Constructors

o RealizeCompleteEvent

Class javax.media.ResourceUnavailableEvent

public class **ResourceUnavailableEvent** extends ControllerErrorEvent

A ResourceUnavailableEvent indicates that a Controller was unable to allocate a resource that it requires for operation.

Version: 1.21, 97/08/23 See Also: Controller, ControllerListener

Constructor Index

o ResourceUnavailableEvent(Controller)o ResourceUnavailableEvent(Controller, String)

Constructors

```
o ResourceUnavailableEvent
```

public ResourceUnavailableEvent(Controller from)

o ResourceUnavailableEvent

Class javax.media.RestartingEvent

public class **RestartingEvent** extends StopEvent

A RestartingEvent indicates that a Controller has moved from the *Started* state back to the *Prefetching* state (a *Stopped* state) and intends to return to the *Started* state when *Prefetching* is complete. This occurs when a *Started* Player is asked to change its rate or media time and to fulfill the request must prefetch its media again.

Version: 1.14, 97/08/23. See Also: Controller, ControllerListener

Constructor Index

o RestartingEvent(Controller, int, int, int, Time)

Constructors

o RestartingEvent

Class javax.media.StartEvent

public class **StartEvent** extends TransitionEvent

StartEvent is a TransitionEvent that indicates that a Controller has entered the *Started* state. Entering the *Started* state implies that syncStart has been invoked, providing a new *media time* to *time-base time* mapping. StartEvent provides the *time-base time* and the *media-time* that *Started* this Controller.

Version:

1.31, 97/08/23

See Also: Controller, ControllerListener

Constructor Index

o **StartEvent**(Controller, int, int, int, Time, Time) Construct a new StartEvent.

Method Index

o getMediaTime()
 Get the clock time (media time) when the Controller started.
o getTimeBaseTime()
 Get the time-base time that started the Controller.

Constructors

o StartEvent

Construct a new StartEvent. The from argument identifies the Controller that is generating this event. The mediaTime and the tbTime identify the *media-time* to *time-base-time* mapping that *Started* the Controller

Parameters:

from - The Controller that has *Started*. mediaTime - The media time when the Controller *Started*. tbTime - The time-base time when the Controller *Started*.

Methods

o getMediaTime

```
public Time getMediaTime()
```

Get the clock time (media time) when the Controller started.

Returns:

The Controller's *media time* when it started.

o getTimeBaseTime

```
public Time getTimeBaseTime()
```

Get the time-base time that started the Controller.

Returns:

The *time-base time* associated with the Controller when it started.

Class javax.media.StopAtTimeEvent

public class **StopAtTimeEvent** extends StopEvent

A StopAtTimeEvent indicates that the Controller has stopped because it reached its stop time.

Version: 1.11, 97/08/23. See Also: Controller, ControllerListener

Constructor Index

o StopAtTimeEvent(Controller, int, int, int, Time)

Constructors

o StopAtTimeEvent

Class javax.media.StopByRequestEvent

public class **StopByRequestEvent** extends StopEvent

A StopByRequestEvent indicates that the Controller has stopped in response to a stop call. This event is posted as an acknowledgement even if the Controller is already *Stopped*.

Version: 1.11, 97/08/23. See Also: Controller, ControllerListener

Constructor Index

o StopByRequestEvent(Controller, int, int, int, Time)

Constructors

o StopByRequestEvent

Class javax.media.StopEvent

```
java.lang.Object
    |
    +----javax.media.ControllerEvent
    |
    +----javax.media.TransitionEvent
    |
    +----javax.media.StopEvent
```

public class **StopEvent** extends TransitionEvent

StopEvent is a ControllerEvent that indicates that a Controller has stopped.

Version: 1.28, 97/08/23 See Also: Controller, ControllerListener

Constructor Index

o StopEvent(Controller, int, int, int, Time)

Method Index

o getMediaTime()

Get the clock time (media time) that was passed into the constructor.

Constructors

o StopEvent

Parameters:

from - The Controller that generated this event. mediaTime - The *media time* at which the Controller stopped.

Methods

o getMediaTime

public Time getMediaTime()

Get the clock time (media time) that was passed into the constructor.

Returns:

The *mediaTime* at which the Controller stopped.

Class javax.media.StopTimeChangeEvent

public class **StopTimeChangeEvent** extends ControllerEvent

A StopTimeChangeEvent is generated by a Controller when its stop time has changed.

Version: 1.12, 97/08/25. See Also: Controller, ControllerListener

Constructor Index

o StopTimeChangeEvent(Controller, Time)

Method Index

o getStopTime()

Get the new stop-time for the Controller that generated this event.

Constructors

o StopTimeChangeEvent

Methods

o getStopTime

```
public Time getStopTime()
```

Get the new stop-time for the Controller that generated this event.

Returns:

The new stop time for the Controller that generated this event.

Class javax.media.StopTimeSetError

public class **StopTimeSetError** extends MediaError

StopTimeSetError is thrown when the stop time has been set on a *Started* Clock and setStopTime is invoked again.

Version:

1.10, 97/08/23.

Constructor Index

o StopTimeSetError(String)

Constructors

o StopTimeSetError

public StopTimeSetError(String reason)

Class javax.media.Time

java.lang.Object | +----javax.media.Time

public class **Time** extends Object

Time abstracts time in the Java Media framework.

Version: 1.10, 97/08/28. See Also: Clock, TimeBase

Variable Index

o nanoseconds Time is kept to a granularity of nanoseconds.o ONE_SECOND

Constructor Index

o **Time**(double) Construct a time in seconds. o **Time**(long) Construct a time in nanoseconds.

Method Index

o getNanoseconds()
 Get the time value in nanoseconds.
 o getSeconds()
 Get the time value in seconds.
 o secondsToNanoseconds(double)
 Convert seconds to nanoseconds.

Variables

o ONE_SECOND

public static final long ONE_SECOND

o nanoseconds

Time is kept to a granularity of nanoseconds. Converions to and from this value are done to implement construction or query in seconds.

Constructors

o Time

```
public Time(long nano)
```

Construct a time in nanoseconds.

Parameters:

nano - Number of nanoseconds for this time.

o Time

public Time(double seconds)

Construct a time in seconds.

Parameters:

seconds - Time specified in seconds.

Methods

o secondsToNanoseconds

protected long secondsToNanoseconds(double seconds)

Convert seconds to nanoseconds.

o getNanoseconds

```
public long getNanoseconds()
```

Get the time value in nanoseconds.

Returns:

The time in nanoseconds.

o getSeconds

```
public double getSeconds()
```

Get the time value in seconds.

Interface javax.media.TimeBase

public interface TimeBase

A TimeBase is a constantly ticking source of time, much like a crystal.

Unlike a Clock, a TimeBase cannot be temporally transformed, reset, or stopped.

Version: 1.13, 97/08/25. See Also: Clock

Method Index

o getNanoseconds()

Get the current time of the TimeBase specified in nanoseconds. o getTime() Get the current time of this TimeBase.

Methods

o getTime

public abstract Time getTime()

Get the current time of this TimeBase.

Returns: the current TimeBase time.

o getNanoseconds

public abstract long getNanoseconds()

Get the current time of the TimeBase specified in nanoseconds.

Returns:

the current TimeBase time in nanoseocnds.

Class javax.media.TransitionEvent

java.lang.Object | +----javax.media.ControllerEvent | +----javax.media.TransitionEvent

public class **TransitionEvent** extends ControllerEvent

TransitionEvent is a ControllerEvent that indicates that a Controller has changed state.

Version: 1.10, 97/08/23 See Also: Controller, ControllerListener

Constructor Index

o **TransitionEvent**(Controller, int, int, int) Construct a new TransitionEvent.

Method Index

o getCurrentState()

Get the Controller's state at the time this event was generated

o getPreviousState()

Get the state that the Controller was in before this event occurred.

o getTargetState()

Get the Controller's target state at the time this event was generated.

Constructors

```
o TransitionEvent
```

Construct a new TransitionEvent.

Parameters:

from - The Controller that is generating this event. previous - The state that the Controller was in before this event. current - The state that the Controller is in as a result of this event. target - The state that the Controller is heading to.

Methods

o getPreviousState

public int getPreviousState()

Get the state that the Controller was in before this event occurred.

Returns:

The Controller's previous state.

o getCurrentState

```
public int getCurrentState()
```

Get the Controller's state at the time this event was generated

Returns:

The Controller's current state.

o getTargetState

public int getTargetState()

Get the Controller's target state at the time this event was generated.

Returns:

The Controller's target state.

Class javax.media.protocol.ContentDescriptor

```
java.lang.Object
|
+----javax.media.protocol.ContentDescriptor
```

public class **ContentDescriptor** extends Object

A ContentDescriptor identifies media data containers.

Version: 1.10, 97/08/26. See Also: SourceStream

Variable Index

o CONTENT_UNKNOWN o typeName

Constructor Index

```
o ContentDescriptor(String)
Create a content descriptor with the specified name.
```

Method Index

o getContentType()
 Obtain a string that represents the content-name for this descriptor.

 o mimeTypeToPackageName(String)
 Map a MIME content-type to an equivalent string of class-name components.

Variables

o CONTENT_UNKNOWN

public static final String CONTENT_UNKNOWN

o typeName

protected String typeName

Constructors

o ContentDescriptor

```
public ContentDescriptor(String cdName)
```

Create a content descriptor with the specified name.

To create a ContentDescriptor from a MIME type, use the mimeTypeToPackageName static member.

Parameters:

cdName - The name of the content-type.

Methods

o getContentType

```
public String getContentType()
```

Obtain a string that represents the content-name for this descriptor.

Returns:

The content-type name.

o mimeTypeToPackageName

protected static final String mimeTypeToPackageName(String mimeType)

Map a MIME content-type to an equivalent string of class-name components.

The MIME type is mapped to a string by:

- 1. Replacing all slashes with a period.
- 2. Converting all alphabetic characters to lower case.
- 3. Converting all non-alpha-numeric characters other than periods to underscores (_).

For example, "text/html" would be converted to "text.html"

Parameters:

mimeType - The MIME type to map to a string.

Interface javax.media.protocol.Controls

public interface Controls

Controls provides an interface for obtaining objects by interface or class name. This is useful in the case where support for a particular interface cannot be determined at runtime, or where a different object is required to implement the behavior. The object returned from getControl is assumed to control the object that getControl was invoked on.

Version:

1.4, 97/08/28.

Method Index

o getControl(String)

Obtain the object that implements the specified Class or Interface The full class or interface name must be used.

o getControls()

Obtain the collection of objects that control the object that implements this interface.

Methods

o getControls

```
public abstract Object[] getControls()
```

Obtain the collection of objects that control the object that implements this interface.

If no controls are supported, a zero length array is returned.

Returns:

the collection of object controls

o getControl

public abstract Object getControl(String controlType)

Obtain the object that implements the specified Class or Interface The full class or interface name must be used.

If the control is not supported then null is returned.

Returns:

the object that implements the control, or null.

Class javax.media.protocol.DataSource

```
java.lang.Object
|
+----javax.media.protocol.DataSource
```

public abstract class **DataSource** extends Object implements Controls, Duration

A DataSource is an abstraction for media protocol-handlers. DataSource manages the life-cycle of the media source by providing a simple connection protocol.

Source Controls

A DataSource might support an operation that is not part of the DataSource class definition. For example a source could support positioning its media to a particular time. Some operations are dependent on the data stream that the source is managing, and support cannot be determined until after the source has been connected.

To obtain all of the objects that provide control over a DataSource, use getControls which returns an array of Object To determine if a particular kind of control is available and obtain the object that implements it, use getControl which takes the name of the Class or Interface that of the desired control.

Version:

1.16, 97/08/26

See Also:

Manager, DefaultPlayerFactory, Positionable, RateConfigureable

Constructor Index

o DataSource()

A no-argument constructor required by pre 1.1 implementations so that this class can be instantiated by calling Class.newInstance.

o DataSource(MediaLocator)

Construct a DataSource from a MediaLocator.

Method Index

o connect()

Open a connection to the source described by the MediaLocator.

o disconnect()

Close the connection to the source described by the locator.

o getContentType()

Get a string that describes the content-type of the media that the source is providing.

o getControl(String)

Obtain the object that implements the specified Class or Interface The full class or interface name must be used.

o getControls()

Obtain the collection of objects that control the object that implements this interface.

o getDuration()

Get the duration of the media represented by this object.

o getLocator()

Get the MediaLocator that describes this source.

o initCheck()

Check to see if this connection has been initialized with a MediaLocator.

o setLocator(MediaLocator)

Set the connection source for this DataSource.

o start()

Initiate data-transfer.

o stop()

Stop the data-transfer.

Constructors

o DataSource

public DataSource()

A no-argument constructor required by pre 1.1 implementations so that this class can be instantiated by calling Class.newInstance.

o DataSource

```
public DataSource(MediaLocator source)
```

Construct a DataSource from a MediaLocator. This method should be overloaded by subclasses; the default implementation just keeps track of the MediaLocator.

Parameters:

source - The MediaLocator that describes the DataSource.

Methods

o setLocator

```
public void setLocator(MediaLocator source)
```

Set the connection source for this DataSource. This method should only be called once; an error is thrown if the locator has already been set.

Parameters:

source - The ${\tt MediaLocator}$ that describes the media source.

o getLocator

```
public MediaLocator getLocator()
```

Get the MediaLocator that describes this source. Returns null if the locator hasn't been set. (Very unlikely.)

Returns:

The MediaLocator for this source.

o initCheck

```
protected void initCheck()
```

Check to see if this connection has been initialized with a MediaLocator. If the connection hasn't been initialized, initCheck throws an UninitializedError. Most methods should call initCheck on entry.

o getContentType

```
public abstract String getContentType()
```

Get a string that describes the content-type of the media that the source is providing.

It is an error to call getContentType if the source is not connected.

Returns:

The name that describes the media content.

o connect

public abstract void connect() throws IOException

Open a connection to the source described by the MediaLocator.

The connect method initiates communication with the source.

Throws: IOException Thrown if there are IO problems when connect is called.

o disconnect

```
public abstract void disconnect()
```

Close the connection to the source described by the locator.

The disconnect method frees resources used to maintain a connection to the source. If no resources are in use, disconnect is ignored. If stop hasn't already been called, calling disconnect implies a stop.

o start

```
public abstract void start() throws IOException
```

Initiate data-transfer. The start method must be called before data is available. (You must call connect before calling start.)

Throws: IOException

Thrown if there are IO problems with the source when start is called.

o stop

public abstract void stop() throws IOException

Stop the data-transfer. If the source has not been connected and started, stop does nothing.

Interface javax.media.protocol.Positionable

public interface Positionable

A DataSource implements the Positionable interface if it supports changing the media position within the stream.

Version: 1.6, 97/08/23. See Also: Datasource

Variable Index

o RoundDowno RoundNearesto RoundUp

Method Index

```
o isRandomAccess()
```

Find out if this source can be repositioned to any point in the stream. o **setPosition**(Time, int) Set the position to the specified time.

Variables

o RoundUp

public static final int RoundUp

o RoundDown

public static final int RoundDown

o RoundNearest

public static final int RoundNearest

Methods

o setPosition

Set the position to the specified time. Returns the rounded position that was actually set.

Parameters:

time - The new position in the stream.

round - The rounding technique to be used: RoundUp, RoundDown, RoundNearest.

Returns:

The actual position set.

o isRandomAccess

public abstract boolean isRandomAccess()

Find out if this source can be repositioned to any point in the stream. If not, the source can only be repositioned to the beginning of the stream.

Returns:

Returns true if the source is random access; false if the source can only be reset to the beginning of the stream.

Class javax.media.protocol.PullDataSource

public abstract class **PullDataSource** extends DataSource

Abstracts a media data-source that only supports pull data-streams.

Version: 1.5, 97/08/23. See Also: Manager, Player, DefaultPlayerFactory, DataSource

Constructor Index

o PullDataSource()

Method Index

```
o getStreams()
```

Get the collection of streams that this source manages.

Constructors

o PullDataSource

```
public PullDataSource()
```

Methods

o getStreams

```
public abstract PullSourceStream[] getStreams()
```

Get the collection of streams that this source manages. The collection of streams is entirely content dependent. The MIME type of this DataSource provides the only indication of what streams can be available on this connection.

Returns:

The collection of streams for this source.

Interface javax.media.protocol.PullSourceStream

public interface **PullSourceStream** extends SourceStream

Abstracts a read interface that data is pulled from.

Version: 1.8, 97/08/23. See Also: PullDataSource

Method Index

o read(byte[], int, int)
Block and read data from the stream.
o willReadBlock()
Find out if data is available now.

Methods

o willReadBlock

```
public abstract boolean willReadBlock()
```

Find out if data is available now. Returns true if a call to read would block for data.

Returns:

Returns true if read would block; otherwise returns false.

o read

Block and read data from the stream.

Reads up to length bytes from the input stream into an array of bytes. If the first argument is null, up to length bytes are read and discarded. Returns -1 when the end of the media is reached. This method only returns 0 if it was called with a length of 0.

Parameters:

buffer - The buffer to read bytes into. offset - The offset into the buffer at which to begin writing data. length - The number of bytes to read.

Returns:

The number of bytes read, -1 indicating the end of stream, or 0 indicating read was called with length 0.

Class javax.media.protocol.PushDataSource

public abstract class **PushDataSource** extends DataSource

Abstracts a data source that manages PushDataStreams.

Version: 1.5, 97/08/23. See Also: Manager, Player, DefaultPlayerFactory, DataSource

Constructor Index

o PushDataSource()

Method Index

```
o getStreams()
```

Get the collection of streams that this source manages.

Constructors

o PushDataSource

```
public PushDataSource()
```

Methods

o getStreams

```
public abstract PushSourceStream[] getStreams()
```

Get the collection of streams that this source manages. The collection of streams is entirely content dependent. The ContentDescriptor of this DataSource provides the only indication of what streams can be available on this connection.

Returns:

The collection of streams for this source.

Interface javax.media.protocol.PushSourceStream

public interface **PushSourceStream** extends SourceStream

Abstracts a read interface that pushes data.

Version: 1.7, 97/08/25. See Also: PushDataSource

Method Index

o getMinimumTransferSize() Determine the size of the buffer needed for the data transfer.
o read(byte[], int, int) Read from the stream without blocking.
o setTransferHandler(SourceTransferHandler) Register an object to service data transfers to this stream.

Methods

o read

Read from the stream without blocking. Returns -1 when the end of the media is reached.

Parameters:

buffer - The buffer to read bytes into. offset - The offset into the buffer at which to begin writing data. length - The number of bytes to read.

Returns:

The number of bytes read or -1 when the end of stream is reached.

o getMinimumTransferSize

```
public abstract int getMinimumTransferSize()
```

Determine the size of the buffer needed for the data transfer. This method is provided so that a transfer handler can determine how much data, at a minimum, will be available to transfer from the source. Overflow and data loss is likely to occur if this much data isn't read at transfer time.

Returns:

The size of the data transfer.

o setTransferHandler

public abstract void setTransferHandler(SourceTransferHandler transferHandler)

Register an object to service data transfers to this stream.

If a handler is already registered when setTransferHandler is called, the handler is replaced; there can only be one handler at a time.

Parameters:

transferHandler - The handler to transfer data to.

Interface javax.media.protocol.RateConfiguration

public interface RateConfiguration

A configuration of streams for a particular rate.

Version:

1.7, 97/08/28. See Also: DataSource, RateConfigureable

Method Index

o getRate()
 Get the RateRange for this configuration.
o getStreams()
 Get the streams that will have content at this rate.

Methods

o getRate

public abstract RateRange getRate()

Get the RateRange for this configuration.

Returns:

The rate supported by this configuration.

o getStreams

public abstract SourceStream[] getStreams()

Get the streams that will have content at this rate.

Returns:

The streams supported at this rate.

Interface javax.media.protocol.RateConfigureable

public interface RateConfigureable

DataSources support the RateConfigureable interface if they use different rate-configurations to support multiple media display speeds.

Version:

1.7, 97/08/26. See Also: DataSource, RateConfiguration, RateRange

Method Index

o getRateConfigurations()
 Get the rate configurations that this object supports.
 o setRateConfiguration(RateConfiguration)
 Set a new RateConfiguration.

Methods

o getRateConfigurations

```
public abstract RateConfiguration[] getRateConfigurations()
```

Get the rate configurations that this object supports. There must always be one and only one for a RateConfiguration that covers a rate of 1.0.

Returns:

The collection of RateConfigurations that this source supports.

o setRateConfiguration

```
public abstract RateConfiguration setRateConfiguration(RateConfiguration config)
```

Set a new RateConfiguration. The new configuration should have been obtained by calling getRateConfigurations. Returns the actual RateConfiguration used.

Parameters: config - The RateConfiguration to use. Returns: The actual RateConfiguration used by the source.

Class javax.media.protocol.RateRange

```
java.lang.Object
|
+----javax.media.protocol.RateRange
```

public class **RateRange** extends Object

Describes the speed at which data flows.

Version:

1.6, 97/08/23.

Constructor Index

 o RateRange(float, float, float, boolean) Constructor using required values.
 o RateRange(RateRange) Copy constructor.

Method Index

o getCurrentRate()
Get the current rate.
o getMaximumRate()
Get the maximum rate supported by this range.
o getMinimumRate()
Get the minimum rate supported by this range.
o isExact()
Determine whether or not the source will maintain a constant speed when using this rate.
o setCurrentRate(float)

Set the current rate.

Constructors

o RateRange

```
public RateRange(RateRange r)
```

Copy constructor.

o RateRange

Constructor using required values.

Parameters:

init - The initial value for this rate.min - The minimum value that this rate can take.max - The maximum value that this rate can take.isExact - Set to true if the source rate does not vary when using this rate range.

Methods

o setCurrentRate

```
public float setCurrentRate(float rate)
```

Set the current rate. Returns the rate that was actually set. This implementation just returns the specified rate, subclasses should return the rate that was actually set.

Parameters:

rate - The new rate.

o getCurrentRate

```
public float getCurrentRate()
```

Get the current rate.

Returns:

The current rate.

o getMinimumRate

```
public float getMinimumRate()
```

Get the minimum rate supported by this range.

Returns:

The minimum rate.

o getMaximumRate

public float getMaximumRate()

Get the maximum rate supported by this range.

Returns:

The maximum rate.

o isExact

Determine whether or not the source will maintain a constant speed when using this rate. If the rate varies, synchronization is usually impractical.

Returns:

Returns true if the source will maintain a constant speed at this rate.

Interface javax.media.protocol.Seekable

public interface Seekable

A SourceStream will implement this interface if it is capable of seeking to a particular position in the stream.

Version:

1.6, 97/08/23. See Also: SourceStream

Method Index

o isRandomAccess()

Find out if this source can position anywhere in the stream.

o seek(long)

Seek to the specified point in the stream.

o tell()

Obtain the current point in the stream.

Methods

o seek

public abstract long seek(long where)

Seek to the specified point in the stream.

Parameters:

where - The position to seek to.

Returns:

The new stream position.

o tell

```
public abstract long tell()
```

Obtain the current point in the stream.

o isRandomAccess

```
public abstract boolean isRandomAccess()
```

Find out if this source can position anywhere in the stream. If the stream is not random access, it can only be repositioned to the beginning.

Returns:

Returns true if the stream is random access, false if the stream can only be reset to the beginning.

Interface javax.media.protocol.SourceStream

public interface **SourceStream** extends Controls

Abstracts a single stream of media data.

Stream Controls

A SourceStream might support an operation that is not part of the SourceStream definition. For example a stream might support seeking to a particular byte in the stream. Some operations are dependent on the stream data, and support cannot be determined until the stream is in use.

To obtain all of the objects that provide control over a stream use getControls. To determine if a particular kind of control is available, and obtain the object that implements the control use getControl.

Version: 1.12, 97/08/28. See Also:

DataSource, PushSourceStream, PullSourceStream, Seekable

Variable Index

o LENGTH_UNKNOWN

Method Index

```
o endOfStream()
```

Find out if the end of the stream has been reached.

o getContentDescriptor()

Get the current content type for this stream.

o getContentLength()

Get the size, in bytes, of the content on this stream.

Variables

o LENGTH_UNKNOWN

public static final long LENGTH_UNKNOWN

Methods

o getContentDescriptor

public abstract ContentDescriptor getContentDescriptor()

Get the current content type for this stream.

Returns:

The current ContentDescriptor for this stream.

o getContentLength

public abstract long getContentLength()

Get the size, in bytes, of the content on this stream. LENGTH_UNKNOWN is returned if the length is not known.

Returns:

The content length in bytes.

o endOfStream

public abstract boolean endOfStream()

Find out if the end of the stream has been reached.

Returns:

Returns true if there is no more data.

Interface javax.media.protocol.SourceTransferHandler

public interface SourceTransferHandler

Implements the callback from a PushSourceStream.

Version: 1.5, 97/08/23. See Also: PushSourceStream

Method Index

o **transferData**(PushSourceStream) Transfer new data from a PushSourceStream.

Methods

o transferData

public abstract void transferData(PushSourceStream stream)

Transfer new data from a PushSourceStream.

Parameters:

stream - The stream that is providing the data.

Class javax.media.protocol.URLDataSource

public class **URLDataSource** extends PullDataSource

A default data-source created directly from a URL using URLConnection.

Version: 1.19, 97/08/28. See Also: URL, URLConnection, InputSourceStream

Variable Index

```
o conn
o connected
o contentType
o sources
```

Constructor Index

```
    o URLDataSource()
Implemented by subclasses.
    o URLDataSource(URL)
Construct a URLDataSource directly from a URL.
```

Method Index

o connect()

Initialize the connection with the source.

o disconnect()

Disconnect the source.

o getContentType()

Return the content type name.
o getControl(String)

Returns null, because this source doesn't provide any controls.

o getControls()

Returns an empty array, because this source doesn't provide any controls.

o getDuration()

Returns Duration.DURATION_UNKNOWN.

o getStreams()

Get the collection of streams that this source manages.

o start()

Initiate data-transfer.

o stop()

Stops the

Variables

o conn

protected URLConnection conn

o contentType

protected ContentDescriptor contentType

o sources

protected URLSourceStream sources[]

o connected

protected boolean connected

Constructors

o URLDataSource

protected URLDataSource()

Implemented by subclasses.

o URLDataSource

public URLDataSource(URL url) throws IOException

Construct a URLDataSource directly from a URL.

Methods

o getStreams

public PullSourceStream[] getStreams()

Get the collection of streams that this source manages.

Overrides:

getStreams in class PullDataSource

o connect

public void connect() throws IOException

Initialize the connection with the source.

Throws: IOException

Thrown if there are problems setting up the connection.

Overrides:

connect in class DataSource

o getContentType

public String getContentType()

Return the content type name.

Returns:

The content type name.

Overrides:

getContentType in class DataSource

o disconnect

public void disconnect()

Disconnect the source.

Overrides:

disconnect in class DataSource

o start

public void start() throws IOException

Initiate data-transfer.

Overrides:

start in class DataSource

o stop

public void stop() throws IOException

Stops the

Overrides: stop in class DataSource

o getDuration

```
public Time getDuration()
```

Returns Duration.DURATION_UNKNOWN. The duration is not available from an InputStream.

Returns:

Duration.DURATION_UNKNOWN. Overrides: getDuration in class DataSource

o getControls

public Object[] getControls()

Returns an empty array, because this source doesn't provide any controls.

Returns:

empty Object array. Overrides: getControls in class DataSource

o getControl

public Object getControl(String controlName)

Returns null, because this source doesn't provide any controls.

Overrides:

getControl in class DataSource

Package Index

Other Packages

- package javax.media
- package javax.media.protocol

Class Hierarchy

- class java.lang.Object
 - interface javax.media.CachingControl (extends javax.media.Control)
 - interface javax.media.Clock
 - class javax.media.protocol.ContentDescriptor
 - interface javax.media.Control
 - interface javax.media.Controller (extends javax.media.Clock, javax.media.Duration)
 - class javax.media.ControllerEvent (implements javax.media.MediaEvent)
 - class javax.media.CachingControlEvent
 - class javax.media.ControllerClosedEvent
 - class javax.media.ControllerErrorEvent
 - class javax.media.ConnectionErrorEvent
 - class javax.media.InternalErrorEvent
 - class javax.media.ResourceUnavailableEvent
 - class javax.media.DurationUpdateEvent
 - class javax.media.MediaTimeSetEvent
 - class javax.media.RateChangeEvent
 - class javax.media.StopTimeChangeEvent
 - class javax.media.TransitionEvent
 - o class javax.media.PrefetchCompleteEvent
 - o class javax.media.RealizeCompleteEvent
 - class javax.media.StartEvent
 - class javax.media.StopEvent
 - class javax.media.DataStarvedEvent
 - class javax.media.DeallocateEvent
 - class javax.media.EndOfMediaEvent
 - class javax.media.RestartingEvent
 - class javax.media.StopAtTimeEvent
 - class javax.media.StopByRequestEvent
 - interface javax.media.ControllerListener
 - interface javax.media.protocol.Controls
 - class javax.media.protocol.DataSource (implements javax.media.protocol.Controls, javax.media.Duration)
 - class javax.media.protocol.PullDataSource
 - class javax.media.protocol.URLDataSource
 - class javax.media.protocol.PushDataSource
 - interface javax.media.Duration
 - class javax.media.GainChangeEvent (implements javax.media.MediaEvent)
 - interface javax.media.GainChangeListener
 - interface javax.media.GainControl (extends javax.media.Control)
 - class javax.media.Manager
 - interface javax.media.MediaEvent
 - interface javax.media.MediaHandler

- class javax.media.MediaLocator
- interface javax.media.MediaProxy (extends javax.media.MediaHandler)
- class javax.media.PackageManager
- interface javax.media.Player (extends javax.media.MediaHandler, javax.media.Controller, javax.media.Duration)
- interface javax.media.protocol.Positionable
- interface javax.media.protocol.PullSourceStream (extends javax.media.protocol.SourceStream)
- interface javax.media.protocol.PushSourceStream (extends javax.media.protocol.SourceStream)
- interface javax.media.protocol.RateConfiguration
- interface javax.media.protocol.RateConfigureable
- class javax.media.protocol.RateRange
- interface javax.media.protocol.Seekable
- interface javax.media.protocol.SourceStream (extends javax.media.protocol.Controls)
- interface javax.media.protocol.SourceTransferHandler
- class java.lang.Throwable (implements java.io.Serializable)
 - class java.lang.Error
 - class javax.media.MediaError
 - class javax.media.ClockStartedError
 - class javax.media.NotPrefetchedError
 - class javax.media.NotRealizedError
 - class javax.media.StopTimeSetError
 - class java.lang.Exception
 - class javax.media.MediaException
 - class javax.media.ClockStoppedException
 - class javax.media.IncompatibleSourceException
 - class javax.media.IncompatibleTimeBaseException
 - class javax.media.NoDataSourceException
 - class javax.media.NoPlayerException
- class javax.media.Time
- interface javax.media.TimeBase